

# **EXT: ReadSpeaker - Online Text to Speech**

Extension Key: readspeaker

Language:

Version: 0.2.0

Keywords: text to speech, web accessibility

Copyright 2012, Oliver Hader, [oliver.hader@typo3.org](mailto:oliver.hader@typo3.org)

This document is published under the Open Content License  
available from <http://www.opencontent.org/opl.shtml>

The content of this document is related to TYPO3

- a GNU/GPL CMS/Framework available from [www.typo3.org](http://www.typo3.org)

# Table of Contents

## EXT: ReadSpeaker - Online Text to Speech..... 1

### Introduction..... 3

What does it do?..... 3

Screenshots..... 3

### Administration..... 4

Configuration..... 4

Most of the settings can be defined by using the constant editor in the TYPO3 back-end. Most

important properties are customerId and readId (see TypeScript reference for further details).... 4

Let's assume that the main content column has the CSS id content-column and thus shall be used as readId, the part of the site to be read by ReadSpeaker..... 4

Content column with CSS id content-column..... 4

### Configuration..... 6

Reference..... 6

### ChangeLog..... 8

# Introduction

## What does it do?

This extension allows to integrate the ReadSpeaker widget in the TYPO3 front-end.

ReadSpeaker (<http://www.readspeaker.com/>) is a service that fetches the contents of a web page and transfers those to spoken words. Thus, this is a good way to deliver kind of a screen reader for your website out of the box.

## Screenshots




ReadSpeaker button that is rendered above the main content column

# Administration

## Configuration

### TypoScript Templates

This extension is shipped with a static template that needs to be included.



Inclusion of static TypoScript in the TYPO3 back-end


## Configuration

Most of the settings can be defined by using the constant editor in the TYPO3 back-end. Most important properties are `customerId` and `readId` (see TypoScript reference for further details).

Let's assume that the main content column has the CSS id `content-column` and thus shall be used as `readId`, the part of the site to be read by ReadSpeaker.



Content column with CSS id `content-column`




Various properties that can be modified in the TYPO3 constant editor

## Disable ReadSpeaker for content elements or pages

The ReadSpeaker feature can be disabled for a whole page or for particular content elements on a page. For content elements the accordant part is wrapped the CSS class `rs-skip`.



Disabling ReadSpeaker for a particular page



Disabling ReadSpeaker for a particular content element

# Configuration

## Reference

### plugin.tx\_readspeaker

Property:	Data type:	Description:	Default:
<b>settings</b>	array	<p>Defines several settings that can be defined in the constant editor.</p> <p><b>Example:</b></p> <pre>settings {     stylesheet = fileadmin/readspeaker.css     customerId = 12345     baseUrl = ...     language = en_en     readId = content-column     renderTo = readspeaker-section     scriptUrl = ...     applicationUrl = ...     buttonStyle = tx-readspeaker-icon-basic }</pre>	
<b>renderObject</b>	cObject	<p>Applies to restricted URLs</p> <p><b>Example:</b></p> <pre>renderObject = COA renderObject {     10 = TEXT     10 {         ...     } }</pre>	

### plugin.tx\_readspeaker.settings

Property:	Data type:	Description:	Default:
<b>stylesheet</b>	string	File name of an alternative CSS stylesheet to be used.	
<b>customerId</b>	integer	The customerId provided by ReadSpeaker, you need a valid contract from <a href="http://www.readspeaker.com/">http://www.readspeaker.com/</a>	
<b>baseUrl</b>	string	<p>Defines an alternative base URL to be used, in case your website is running on different domains and the currently used domain not activated in your ReadSpeaker account.</p> <p><b>Example:</b></p> <p>Assume that baseUrl is set to the following value  <a href="http://www.mydomain.com">http://www.mydomain.com</a>  then  <a href="http://test.local/home.html?query=value">http://test.local/home.html?query=value</a>  will be modified to  <a href="http://mydomain.com/home.html?query=value">http://mydomain.com/home.html?query=value</a></p>	
<b>language</b>	string	The dictionary to be used (e.g. en_en, de_de, fr_fr, ...)	en_en
<b>voice</b>	String	Optional voice to be used (e.g. de_hans, ...)	
<b>readId</b>	string	CSS id to be used to determine the contents to be read.	

Property:	Data type:	Description:	Default:
<b>renderTo</b>	string	<p>CSS id to be used to render the ReadSpeaker widget to.</p> <p><b>Example:</b></p> <pre>&lt;div id="readspeaker-section"&gt; will be extended to contain the ReadSpeaker widget &lt;div id="readspeaker-section"&gt;   &lt;div id="tx-readspeaker-widget-1"     class="tx-readspeaker-widget rs_skip"&gt;     ...   &lt;/div&gt;</pre>	
<b>scriptUrl</b>	string	<p>(internal)</p> <p>URL of the ReadSpeaker JavaScript</p>	
<b>applicationUrl</b>	string	<p>(internal)</p> <p>URL of the ReadSpeaker application reading texts</p>	
<b>buttonStyle</b>	string	<p>CSS class name of the "read text" button to be used.</p>	

# ChangeLog

Version:	Changes:
<b>0.2.0</b>	Update constant editor screenshot, add baseUrl & voice properties
<b>0.1.0</b>	Initial version of this documentation