

Environment - Windows 11Pro

Browser - Google Chrome Version 106.0.5249.103

Precondition - On the site in the Google Chrome browser, a page with the "Forgot password" form is opened

ID	Title	Steps	Expected Result	Status	Bug link
1	Sending a valid email	1. Enter a valid email address in the email field.	1. A valid email address is displayed in the email input field.	Pass	
		2. Click on the button "Send password reset email".	2. The message "A new password has been sent to your email" is displayed.	Pass	
2	Sending an invalid email	1. Enter an invalid email address in the email field.	1. An invalid email address is displayed in the email input field.	Pass	
		2. Click on the button "Send password reset email".	2. A message is displayed: "Enter a valid email address".	Pass	
3	Sending an empty field	1. Leave the field blank and click "Send password reset email".	1. A message is displayed: "Enter a valid email address"	Pass	
4	Sending a field with numbers	1. Enter numbers in the email field.	1. A field with entered numbers is displayed.	Pass	
		2. Click on the button "Send password reset email".	2. A message is displayed: "Enter a valid email address".	Pass	
5	Sending email without the @ symbol	1. Entering email without the @ symbol.	1. The entered email address is displayed without the @ symbol.	Pass	
		2. Click on the button "Send password reset email".	2. A message is displayed: "Enter a valid email address".	Pass	
6	Sending email with two @ characters	1. Entering email with two @ characters.	1. The entered email address is displayed with two @ characters.	Pass	
		2. Click on the button "Send password reset email".	2. A message is displayed: "Enter a valid email address".	Pass	
7	Sending special characters, such as !#\$%^&*()_+"?><:{	1. Entering email only with special characters, such as !#\$%^&*()_+"?><:{ .	1. The entered email address is displayed with special characters.	Pass	
		2. Click on the button "Send password reset email".	2. A message is displayed: "Enter a valid email address".	Pass	
8	Testing the "Cancel" button	1. Enter invalid email.	1. An invalid email address is displayed in the email input field.	Pass	
		2. Press the "Cancel" button.	2. The entered email address is deleted and an empty input field is displayed again.	Pass	