



ZeroHook-HV Line up Official Support Guide
(Read this guide CAREFULLY or else it could result
in fatal boot errors)

!JOIN DISCORD BELOW TO RECEIVE CUSTOM
BUILD!

<https://discord.com/invite/zerohook>

Date Of Creation
6/7/2023

Any and all users are allowed to share this document as they please in order to help out other members

[REQUIREMENTS OF SYSTEM]

[Winver]

>1909 - 22h2 WIN10)

(All win10 is supported BUT may not load properly or function as it should, proceed with caution, 22h2 is HIGHLY recommended for INTEL and AMD)

-6th gen Intel CPU's to CURRENT GEN

(Some Old chips do not support VIRT)

-All Ryzen CPUS are supported

-Playing with a laptop should always have caution, they are frequently built in with security chips that will prevent the bypass from loading, some pre built PC's also do not have proper settings on their motherboards

-Lenovo


-DELL(Excluding alienware

START HERE FOR ALL PRODUCTS:

These instructions take about 20 minutes to complete and are required for all products. Do the setups for Windows first and then the BIOS setup. These instructions will not permanently change your system and are easily reverted back to their original state after you are done using any product.

Step One: WINDOWS SYSTEM SETTINGS:


1. Start menu > type winver.
 - a. Check what versions are supported on the product!
 - b. [Click here](#) windows update link to swap versions if needed. Changing windows version is very easy and usually does not require loss of data!
2. Start menu > search Virus & threat protection
 - a. Disable “Windows 10 Real-time protection”.



3. Start menu > search Smart screen

a. Disable “Windows 10 Exploit Protection” options.

b. Disable “Windows 10 Reputation-based Protection”.





4. Disabling UAC and Windows Defender Permanently

a. Downloads Winaero Tweaker from this link below

[Winaero Tweaker](#)


b. Run the installer on the program, once open, search “UAC”, select “Disable UAC”, then search “defender” and select “Disable Windows Defender”.



Step Two: General Settings

(Placement of settings will be different from brand to brand)

1. Disabling secure boot and resetting keys



(Make sure all keys read back as 0)

1. Disable all overlays (Geforce Experience, MSI Afterburner, Xbox Gamebar, Discord, Steam, etc)
2. You must remove any pin and/or password on your Windows user account.
3. You must have GPT structure on your disk drive, not MBR.

- Open CMD > enter diskpart > enter list disk > validate your Windows drive is GPT

Disk ###	Status	Size	Free	Dyn	Gpt
Disk 0	Online	931 GB	0 B	*	*

- If Windows doesn't boot, set BIOS mode from Legacy + UEFI to be UEFI only

Bios Settings

4: Ensure settings in bios are as displayed here!

[INTEL]

UEFI	ENABLED
Intel Virtualization(VT-X & VT-D)	ENABLED
CSM	DISABLED
SECURE BOOT	DISABLED
FAST BOOT	DISABLED
TPM	DISABLED


[AMD]

UEFI	ENABLED
AMD Virt (SVM & NX MODE)	ENABLED
CSM	DISABLED
SECURE BOOT	DISABLED
FAST BOOT	DISABLED
TPM	DISABLED

[System updates]

(MAKE SURE YOU HAVE UPDATES ENABLED)
**THE BYPASS WILL NOT LOAD IF ALL UPDATES ARE NOT
INSTALLED**

1. Windows Search > Check for Updates
2. When on 22h2, install ALL AVAILABLE UPDATES



3. Click check for updates right there, if any updates appear, click install, once done windows should ask you to restart your system
4. "Runtime or render error"
 - a. Download the [Direct X SDK from this Link](#)
 - b. Download the [AIO Runtime Installer From This Link](#)

[ESSENTIALS/FIXES]

1. If cheat performance is sluggish, disable “Skeletons” and turn draw distance of entities(Items, Ai, Players) down to 350 meters
2. “Stuck on Windows Boot” you must be on Win10 22h2 and install ALL updates in “Check For Updates”, or else it will be stuck on windows boot and can result in a brick of your system.
3. “Exploit Is Not Loaded”
 - a. Look over all steps above and ensure all was done properly
 - b. Windows may be restricting injection of bypass, a full system wipe from a downloaded .ISO is recommended
4. “I cannot see the menu”
 - a. Make sure you are borderless on Escape From Tarkov.
5. “Runtime or render error”
 - c. Download the [Direct X SDK from this Link](#)
 - d. Download the [AIO Runtime Installer From This Link](#)
6. “I bsod a lot” Disable hyper-v within WINDOWS... not ur bios...
7. “ESP keeps crashing”/”ESP Keeps Crashing”, disable paging file