

You can display all available commands with the help command:

Example

```
C:\Users\myuser>help
```

ASSOC	Displays or modifies file extension associations.
ATTRIB	Displays or changes file attributes.
BREAK	Sets or clears extended CTRL+C checking.
BCDEDIT	Sets properties in boot database to control boot loading.
CACLS	Displays or modifies access control lists (ACLs) of files.
CALL	Calls one batch program from another.
CD	Displays the name of or changes the current directory.
CHCP	Displays or sets the active code page number.
CHDIR	Displays the name of or changes the current directory.
CHKDSK	Checks a disk and displays a status report.
CHKNTFS	Displays or modifies the checking of disk at boot time.
CLS	Clears the screen.
CMD	Starts a new instance of the Windows command interpreter.
COLOR	Sets the default console foreground and background colors.
COMP	Compares the contents of two files or sets of files.
COMPACT	Displays or alters the compression of files on NTFS partitions.
CONVERT	Converts FAT volumes to NTFS. You cannot convert the current

drive.

COPY	Copies one or more files to another location.
DATE	Displays or sets the date.
DEL	Deletes one or more files.
DIR	Displays a list of files and subdirectories in a directory.
DISKPART	Displays or configures Disk Partition properties.
DOSKEY	Edits command lines, recalls Windows commands, and creates macros.
DRIVERQUERY	Displays current device driver status and properties.
ECHO	Displays messages, or turns command echoing on or off.
ENDLOCAL	Ends localization of environment changes in a batch file.
ERASE	Deletes one or more files.
EXIT	Quits the CMD.EXE program (command interpreter).
FC	Compares two files or sets of files, and displays the differences between them.
FIND	Searches for a text string in a file or files.
FINDSTR	Searches for strings in files.
FOR	Runs a specified command for each file in a set of files.
FORMAT	Formats a disk for use with Windows.
FSUTIL	Displays or configures the file system properties.

FTYPE	Displays or modifies file types used in file extension associations.
GOTO	Directs the Windows command interpreter to a labeled line in a batch program.
GPRESULT	Displays Group Policy information for machine or user.
GRAFTABL	Enables Windows to display an extended character set in graphics mode.
HELP	Provides Help information for Windows commands.
ICACLS	Display, modify, backup, or restore ACLs for files and directories.
IF	Performs conditional processing in batch programs.
LABEL	Creates, changes, or deletes the volume label of a disk.
MD	Creates a directory.
MKDIR	Creates a directory.
MKLINK	Creates Symbolic Links and Hard Links.
MODE	Configures a system device.
MORE	Displays output one screen at a time.
MOVE	Moves one or more files from one directory to another directory.
OPENFILES	Displays files opened by remote users for a file share.
PATH	Displays or sets a search path for executable files.
PAUSE	Suspends processing of a batch file and displays a message.
POPD	Restores the previous value of the current directory saved by PUSH.D.

PRINT	Prints a text file.
PROMPT	Changes the Windows command prompt.
PUSHD	Saves the current directory then changes it.
RD	Removes a directory.
RECOVER	Recovers readable information from a bad or defective disk.
REM	Records comments (remarks) in batch files or CONFIG.SYS.
REN	Renames a file or files.
RENAME	Renames a file or files.
REPLACE	Replaces files.
RMDIR	Removes a directory.
ROBOCOPY	Advanced utility to copy files and directory trees.
SET	Displays, sets, or removes Windows environment variables.
SETLOCAL	Begins localization of environment changes in a batch file.
SC	Displays or configures services (background processes).
SCHTASKS	Schedules commands and programs to run on a computer.
SHIFT	Shifts the position of replaceable parameters in batch files.
SHUTDOWN	Allows proper local or remote shutdown of machine.
SORT	Sorts input.
START	Starts a separate window to run a specified program or command.

SUBST	Associates a path with a drive letter.
SYSTEMINFO	Displays machine specific properties and configuration.
TASKLIST	Displays all currently running tasks including services.
TASKKILL	Kill or stop a running process or application.
TIME	Displays or sets the system time.
TITLE	Sets the window title for a CMD.EXE session.
TREE	Graphically displays the directory structure of a drive or path.
TYPE	Displays the contents of a text file.
VER	Displays the Windows version.
VERIFY	Tells Windows whether to verify that your files are written correctly to a disk.
VOL	Displays a disk volume label and serial number.
XCOPY	Copies files and directory trees.
WMIC	Displays WMI information inside interactive command shell.

Command Help

For more information on a specific command, type help + command-name

Example

```
C:\Users\myuser>help date
```

Displays or sets the date.

DATE [/T | date]

Type DATE without parameters to display the current date setting and a prompt for a new one. Press ENTER to keep the same date.

If Command Extensions are enabled the DATE command supports the /T switch which tells the command to just output the current date, without prompting for a new date.