



Private Server Setup Step-by-Step Procedure

- 1) Go to huggingface.co and create a hugging face account and verify email if you haven't already




- 2) Click on the link below

<https://huggingface.co/spaces/realprudhvi/private-exporter-server/tree/main>



- 3) Click on the three dots and then “Duplicate this Space”



- 4) Click on the “Visibility” then choose “Private” and then “Duplicate Space”

Duplicate this Space

Owner

prudhvi-varma

Space name

private-exporter-server

Visibility

Public

Public

Private

Space hardware

Free

CPU Basic



ZeroGPU

Custom Hardware


Duplicate Space

Cancel

5) Wait till the server status changes from “Building” to “Running” (please wait for 3-5 mins)



6) Click on copy icon and paste it on notepad for later use (Step 11)



7) Click on the profile in the top right corner, then click on “Access Tokens”

Profile

 prudhvi-varma

• Notifications

Inbox (0)

+ New Model

+ New Dataset

+ New Space

+ New Collection

Create organization

Usage Quota

Private Storage 0 GB/100 GB

Zero GPU 0/4 min

Inference Usage \$0.00 / \$0.10

Get Hugging Face PRO →


Settings

Access Tokens


Billing

Changelog


Sign Out




- 8) Click on “Create new token”, choose “Read” and then click on “Create token”



- 9) Copy your Access Token and paste it on notepad if needed and click “Done”



10) verify that the access token has been created



11) Go to the current Document_Suite_for_ChatGPT folder and then open background.js
Replace this part with the current space Url (from step 6)

```
const SERVER_URL = "https://realprudhvi-chatgpt-exporter-server.hf.space/export";  
const HF_TOKEN = "";
```


Replace the highlighted section from section, and paste your Access Token

```
const SERVER_URL = "https://prudhvi-varma/private-exporter-server.hf.space/export";  
const HF_TOKEN = "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";
```

Replace the / with –

```
}  
  
const SERVER_URL = "https://prudhvi-varma/private-exporter-server.hf.space/export";  
const HF_TOKEN = "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";  
  
const SERVER_URL = "https://prudhvi-varma-private-exporter-server.hf.space/export";  
const HF_TOKEN = "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";
```

12) Go to chrome://extensions and reload the extension



13) Refresh chatgpt.com to use the private server

Note:

The Hugging Face Space hosting your private server automatically enters sleep mode after 48 hours of inactivity. During this period, the server is temporarily inactive. Upon receiving a new request, the server will automatically restart and resume operation. Please note that the first response after inactivity may experience a slight delay due to the server boot-up process. No manual intervention is required to restart the server.