

Muhieddeen TV Caspar CG Working Documentation.

Logo



Sl. No.	Description	Variable	Value Type	Default Value	Possible Value(s)	Additional Info
1	To show/hide logo	logo	<string>	off	on/off	on – To show logo off – To hide logo
2	Move Horizontal	logoX	<number>	0		Accept Integer/Float value
3	Move Vertical	logoY	<number>	0		Accept Integer/Float value
4	Set logo size	logoSize	<number>	175		Accept Integer/Float value

Water Mark



Sl. No.	Description	Variable	Value Type	Default Value	Possible Value(s)	Additional Info
1	To show/hide water mark	waterMark	<string>	on	on/off	on – To show logo off – To hide logo
2	Move Horizontal	waterMarkX	<number>	0		Accept Integer/Float value
3	Move Vertical	waterMarkY	<number>	0		Accept Integer/Float value
4	Set water mark font size	waterMarkSize	<number>	30		Accept Integer/Float value


5	Set opacity	waterMarkO	<number>	5		Accept Integer/Float value
6	Water Mark Text	waterMarkText	<string>	MuhieddeenTV		

Live



Sl. No.	Description	Variable	Value Type	Default Value	Possible Value(s)	Additional Info
1	To show/hide live	live	<string>	off	on/off	on – To show logo off – To hide logo
2	Move Horizontal	liveX	<number>	0		Accept Integer/Float value
3	Move Vertical	liveY	<number>	0		Accept Integer/Float value
4	Set live font size and padding	liveSize	<number>	30		Accept Integer/Float value
5	Set live style	liveStyle	<string>		s1	


Clock



Sl. No.	Description	Variable	Value Type	Default Value	Possible Value(s)	Additional Info
1	To show/hide clock	clock	<string>	off	on/off	on – To show logo off – To hide logo
2	Move Horizontal	clockX	<number>	0		Accept Integer/Float value
3	Move Vertical	clockY	<number>	0		Accept Integer/Float value
4	Set clock font size	clockSize	<number>	20		Accept Integer/Float value
5	Change clock style	clockStyle	<string>		s1	

6	Update format	clockFormat	<string>	null	hh-mm	Default with show seconds. hh-mm – show without seconds.
---	---------------	-------------	----------	------	-------	---


Ticker



Sl. No.	Description	Variable	Value Type	Default Value	Possible Value(s)	Additional Info
1	To show/hide Ticker	ticker	<string>	off	on/off	on – To show logo off – To hide logo
2	To show /hide Ticker Title	tickerTitle	<string>	on	on/off	on – To show logo off – To hide logo
3	Move Horizontal	tickerX	<number>	0		Accept Integer/Float value
4	Move Vertical	tickerY	<number>	0		Accept Integer/Float value
5	Set Ticker text size	tickerSize	<number>	30		Accept Integer/Float value
6	Update top/bottom padding	tickerPadding	<number>	null		Accept Integer/Float value
7	Update font family (English/Tamil/Arabic)	tickerFont	<string>	Default font will be english font.	Arabic: ar1, ar2, ar3, ar4, ar5 Tamil: ta1, ta2, ta3, ta4	
8	Update Ticker Style	tickerStyle	<string>	s1	s1, s2, ... s10	This will update theme of the ticker
9	Update Ticker Title Background Color	tickerTitleBg	<string>	null	Any color code that you like	This will update only Ticker Title Background color.

10	Update Ticker Title Text Color	tickerTitleColor	<string>	null	Any color code that you like	This will update only Ticker Title Text color.
11	Update Ticker Background Color	tickerBg	<string>	null	Any color code that you like	This will update only Ticker Background color.
12	Update Ticker Text Color	tickerColor	<string>	null	Any color code that you like	This will update only Ticker Text color.
13	Update Ticker Title Text Size	tickerTitleSize	<string>	null		Update Ticker Title Text Size
14	Add Ticker Title Text	tickerTitleText	<string>	Updates	Title text	
15	Add Ticker Text	tickerText	<string>	null	Ticker Text(s)	Text that you want to ticker followed by semi-colon(;) .
16	Set Ticker Height	tickerHeight	<number>	50		Define size of the ticker height
17	Set how many Ticker row to display	tickerRow	<number>	1		Define how many row to display
18	Set Ticker Speed	tickerSpeed	<number>	6		Define Ticker Speed
19	Set Ticker Direction	tickerDirection	<number>	1	1 (or) 2	1 – Ticker go up 2 – Ticker go down
20	Set Ticker hold duration	tickerDuration	<number>	4		Define how many seconds to hold each ticker

News Scroller



Sl. No.	Description	Variable	Value Type	Default Value	Possible Value(s)	Additional Info
1	To show/hide News Scroller	news	<string>	off	on/off	on – To show logo off – To hide logo
2	To show /hide News Scroller Title	newsTitle	<string>	on	on/off	on – To show logo off – To hide logo
3	Move Vertical	newsY	<number>	0		Accept Integer/Float value. This is always stay bottom of the screen. You will give value to move up.

4	Set News Scroller/News Title text size	newsSize	<number>	25		Accept Integer/Float value
5	Update top/bottom padding	newsPadding	<number>	null		Accept Integer/Float value
6	Update news scroller font family (English/Tamil/Arabic)	newsFont	<string>	Default font will be english font.	Arabic: ar1, ar2, ar3, ar4, ar5 Tamil: ta1, ta2, ta3, ta4	
7	Update News Theme Style	newsStyle	<string>	s1	s1, s2, ... s10	This will update theme of the News
8	Update News Title Background Color	newsTitleBg	<string>	null	Any color code that you like	This will update only Ticker Title Background color. If you add this property newsStyle will not be effective
9	Update News Title Text Color	newsTitleColor	<string>	null	Any color code that you like	This will update only Ticker Title Text color. If you add this property newsStyle will not be effective
10	Update News Scroller Background Color	newsBg	<string>	null	Any color code that you like	This will update only Ticker Background color. If you add this property newsStyle will not be effective
11	Update News Text Color	newsColor	<string>	null	Any color code that you like	This will update only Ticker Text color. If you add this property newsStyle will not be effective
12	Add News Title Text	newsTitleText	<string>	News	Title text	
13	Add News Text	newsText	<string>	null	News Text(s)	Text that you want to news scroll followed by semi-colon(;) .
14	Set News Scrolling Speed	newsSpeed	<number>	5		Define News Scrolling Speed
15	Set News Scrolling Direction	newsDirection	<string>	rtl	rtl (or) ltr	rtl – News Scrolling from right to left and News Title stay on left side. ltr – News Scrolling from left to right and News Title stay on right side.
16	Set News Scrolling or not	newsMove	<boolean>	true	true/false	Define the news scrolling to move or not

Title Banner – Full Stretch

UROOS MUBARAK
MUHIEDDEEN ABDUL QADIR JEELANI RALIYALLAHU ANHU

Sl. No.	Description	Variable	Value Type	Default Value	Possible Value(s)	Additional Info
1	To show/hide Title Banner	banner	<string>	off	on/off	on – To show logo off – To hide logo
2	Move Vertical	bannerY	<number>	0		Accept Integer/Float value. This is always stay bottom of the screen. You will give value to move up.
3	Set Banner text size	bannerSize	<number>			Accept Integer/Float value
4	Update Banner Height	bannerH	<number>	null		Accept Integer/Float value
5	Update Banner font family (English/Tamil/Arabic)	bannerFont	<string>	Default font will be english font.	Arabic: ar1, ar2, ar3, ar4, ar5 Tamil: ta1, ta2, ta3, ta4	Define Banner title and sub-title font family.
6	Update Banner sub-title font family (English/Tamil/Arabic)	bannerText1Font	<string>	Default font will be english font.	Arabic: ar1, ar2, ar3, ar4, ar5 Tamil: ta1, ta2, ta3, ta4	Define Banner sub-title font family.
7	Update Banner main title font family (English/Tamil/Arabic)	bannerText2Font	<string>	Default font will be english font.	Arabic: ar1, ar2, ar3, ar4, ar5 Tamil: ta1, ta2, ta3, ta4	Define Banner title and main-title font family.
8	Add Banner sub title text	bannerText1	<string>			Adding sub title of the banner
9	Add Banner main title text	bannerText2	<string>			Adding main title of the banner