

```
mv-connection-gi45tp1bocp.messaging.solace.cloud - PuTTY
This Solace product is proprietary software of
Solace Corporation. By accessing this Solace product
you are agreeing to the license terms and conditions
located at http://www.solace.com/license-software

Copyright 2004-2023 Solace Corporation. All rights reserved.

Operating Mode: Message Routing Node

developer-production-9f12f3i2u1k-solace-primary-0> enable
developer-production-9f12f3i2u1k-solace-primary-0# configure
developer-production-9f12f3i2u1k-solace-primary-0(configure)# message-spool mess
age-vpn myservice
developer-production-9f12f3i2u1k-solace-primary-0(configure/message-spool)# crea
te queue queue01
# max-spool-usage 500
developer-production-9f12f3i2u1k-solace-primary-0(configure/message-spool/queue)
# permission all consume
developer-production-9f12f3i2u1k-solace-primary-0(configure/message-spool/queue)
# no shut
developer-production-9f12f3i2u1k-solace-primary-0(configure/message-spool/queue)# show queue queue01

Flags Legend:
I - Ingress Admin State (U=Up, D=Down)
E - Egress Admin State (U=Up, D=Down)
A - Access-Type (E=Exclusive, N=Non-Exclusive)
S - Selector (Y=Yes, N=No)
D - Durability (D=Durable, N=Non-Durable)
P - Priority (Y=Yes, N=No)

Queue Name      Messages      Spool      Bind Status
Message VPN     Spooled      Usage(MB)  HWM (MB)  Count I E A S D P
-----
```

```
mv-connection-gi45tp1bocp.messaging.solace.cloud - PuTTY

Name              : queue01
Message VPN       : myservice
Durability        : Durable
Id                : 14
Admin Ingress     : Up
Admin Egress      : Up
Access Type       : Exclusive
Partition Count   : 0
Owner             :
Created by mgmt   : Yes
All Others Permission : Consume (1100)
Quota (MB)        : 500
Respect Message Priority : No
Respect TTL       : No
Max TTL (Seconds) : 0 (Disabled)
Well Known        : Yes
Reject Msg to Sender on Discard : Yes
  Including When Shutdown : No
Bind Time Forwarding Mode : Store-And-Forward
Current Messages Spooled : 0
Current Spool Usage (MB) : 0.0000
High Water Mark (MB) : 0.0000
Total Delivered Unacked Msgs : 0
Max Delivered Unacked Msgs Per Flow : 10000
Total Acknowledgments In-Progress : 0
Redelivery        : Enabled
  Max Redelivery : 0
  Redelivery Delay : Disabled
    Multiplier : 2.00
    Initial Interval (ms) : 1000
    Max Interval (ms) : 64000
---Press any key to continue, or 'q' to quit---
```

```
my-connection-gi45p1bocp.messaging.solace.cloud - PuTTY
Quota (MB) : 500
Respect Message Priority : No
Respect TTL : No
Max TTL (Seconds) : 0 (Disabled)
Well Known : Yes
Reject Msg to Sender on Discard : Yes
Including When Shutdown : No
Bind Time Forwarding Mode : Store-And-Forward
Current Messages Spooled : 0
Current Spool Usage (MB) : 0.0000
High Water Mark (MB) : 0.0000
Total Delivered Unacked Msgs : 0
Max Delivered Unacked Msgs Per Flow : 10000
Total Acknowledgments In-Progress : 0
Redelivery : Enabled
Max Redelivery : 0
Redelivery Delay : Disabled
Multiplier : 2.00
Initial Interval (ms) : 1000
Max Interval (ms) : 64000
---Press any key to continue, or 'q' to quit---
Command aborted.
developer-production-9f12f3i2u1k-solace-primary-0(configure)#
developer-production-9f12f3i2u1k-solace-primary-0(configure)# subscription topic hellocli03

Invalid command input
subscription topic hellocli03
^
-> unknown command, or command not available in current mode
developer-production-9f12f3i2u1k-solace-primary-0(configure)# message-spool message-vpn myservice
developer-production-9f12f3i2u1k-solace-primary-0(configure/message-spool)# queue queue01
developer-production-9f12f3i2u1k-solace-primary-0(configure/message-spool/queue)# subscription topic hellocli03
developer-production-9f12f3i2u1k-solace-primary-0(configure/message-spool/queue)#
```