



(3) WhatsApp x NetScaler Gateway x Service details | PubSub+ Cloud x Login x Untitled document - Google Doc x +

docs.google.com/document/d/1J14zh0d2qg8pVYKt049j7PqKMrm6z--m6R2e1gZo_g/edit

Untitled document ☆ Share

File Edit View Insert Format Tools Extensions Help

100% Normal text Arial 11 B I U A

Editing

1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18

12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27

→ In solace go to Management acc
Open putty->open connection->ch

Putty Configuration

Category:

- Session
- Logging
- Terminal
- Keyboard
- Bell
- Features
- Window
- Appearance
- Behaviour
- Translation
- Selection
- Colours
- Connection
- Date
- Proxy
- SSH
- Serial
- Telnet
- Rlogin
- SUPDUP

Configure the appearance of PuTTY's window

Adjust the use of the cursor

Cursor appearance:

- ☒ Block
- ☐ Underline
- ☐ Vertical line

☐ Cursor blinks

Font settings

Font used in the terminal window

Font: Courier New, 10-point [Change...](#)

☐ Allow selection of variable-pitch fonts

Font quality:

- ☐ Antialiased
- ☐ Non-Antialiased
- ☒ ClearType
- ☒ Default

Adjust the use of the mouse pointer

☐ Hide mouse pointer when typing in window

Adjust the window border

Gap between text and window edge: 1

☐ Sunken-edge border (slightly thicker)

[Open](#) [Cancel](#)

And in appearance change the size to 16

Type here to search

30°C Mostly cloudy 13:12 09-08-2023

MYService

Open PubSub+ Broker Manager

Messaging Activity

0% Active Connections

AMQP 0
MQTT 0
SMF 0
REST 0
Web 0

Availability and Versioning

Service State: Running

Created By: KASTURI SRAVANI (sraavanichowdarykasturi@gmail.com)

DMR Cluster

Hostname: mr-connection-gj45bp3bocp.messaging.solace.cloud

Cluster Name: cluster-aks-centralindia-9f12f3i2u1k

Cluster Password: *****

Message VPN: myservice

Primary Router Name: apnk8i4cp0pprimary

PUTTY Configuration

Category: Session, Logging, Terminal, Keyboard, Bell, Features, Window, Appearance, Behaviour, Translation, Selection, Colours, Connection, Date, Proxy, SSH, Serial, Telnet, Plugin, SUFOUP

Options controlling the connection

Sending of null packets to keep session active: 1

Seconds between keepalives (0 to turn off): 1

Low-level TCP connection options

☒ Disable Nagle's algorithm (TCP_NODELAY option)

☐ Enable TCP keepalives (SO_KEEPALIVE option)

Internet protocol version

☒ Auto ☐ IPv4 ☐ IPv6

Logical name of remote host

Logical name of remote host (e.g. for SSH key lookup):

High Availability: Single Node

0% Queue Usage

Messages Queued: 0

Spool Usage: 0.00 KB

MYService

Host Name: mr-connection-gj45bp3bocp.messaging.solace.cloud

Message VPN: myservice

Management Access

Basic Authentication: Enabled

Management Editor Username: myservice-admin

Management Editor Password: havnj0kulc3j0340bklv/770q2

Management Viewer Username: myservice-view

Management Viewer Password: *****

LDAP Authentication: Disabled

SSO Authentication: Disabled

Upgrades

Service has not yet been upgraded

Scale Up

login as:
login as:
login as: myservice-admin
Pre-authentication banner message from server:
Solace PubSub+ Enterprise
End of banner message from server
Keyboard-interactive authentication prompts from server:
Password:
End of keyboard-interactive prompts from server
Solace PubSub+ Enterprise Version 10.4.1.59
This Solace product is proprietary software of Solace Corporation. By accessing this Solace product you are agreeing to the license terms and conditions located at <http://www.solace.com/license-software>
Copyright 2004-2023 Solace Corporation. All rights reserved.
Operating Mode: Message Routing Node
developer-production-9f12f3i2u1k-solace-primary-0>

```
PUTTY (inactive)
Solace Corporation. By accessing this Solace product
you are agreeing to the license terms and conditions
located at http://www.solace.com/license-software

Copyright 2004-2023 Solace Corporation. All rights reserved.

Operating Mode: Message Routing Node

developer-production-9f12f3i2ulk-solace-primary-0> dir
drwxr-xr-x appuser 10002 21 Jul 28 09:32 certs
drwxr-xr-x appuser 10002 6 Jul 28 09:32 cliscripts
drwxr-xr-x appuser 10002 39 Jul 28 09:33 configs
drwxrwxr-x root 10002 4096 Aug 13 08:33 cores
drwxr-xr-x appuser 10002 6 Jul 28 09:32 keytabs
drwxr-xr-x appuser 10002 209 Aug 12 13:48 logs
developer-production-9f12f3i2ulk-solace-primary-0> cd logs
developer-production-9f12f3i2ulk-solace-primary-0> dir
-rw-r--r-- appuser 10002 208143 Aug 13 16:28 command.log
-rw-r--r-- appuser 10002 3850889 Aug 13 16:28 debug.log
-rw-r--r-- appuser 10002 52430839 Aug 12 13:48 debug.log.1
-rw-r--r-- appuser 10002 47772049 Aug 13 16:28 event.log
-rw-r--r-- appuser 10002 52439187 Aug 11 22:25 event.log.1
-rw-r--r-- appuser 10002 52446542 Aug 10 00:19 event.log.2
-rw-r--r-- appuser 10002 52443341 Aug 08 02:10 event.log.3
-rw-r--r-- appuser 10002 52431483 Aug 06 04:01 event.log.4
-rw-r--r-- appuser 10002 52445065 Aug 04 05:48 event.log.5
-rw-r--r-- appuser 10002 3917 Aug 13 04:55 kernel.log
-rw-r--r-- appuser 10002 1345359 Aug 13 16:12 system.log
developer-production-9f12f3i2ulk-solace-primary-0> enable
developer-production-9f12f3i2ulk-solace-primary-0# config
developer-production-9f12f3i2ulk-solace-primary-0(configure)# home
developer-production-9f12f3i2ulk-solace-primary-0> exit
developer-production-9f12f3i2ulk-solace-primary-0> █
```

```
mi-connection-gj45bp3bocp.messaging.solace.cloud - PuTTY
developer-production-9f12f3i2ulk-solace-primary-0> cd logs
developer-production-9f12f3i2ulk-solace-primary-0> dir
-rw-r--r-- appuser 10002 209958 Aug 13 16:30 command.log
-rw-r--r-- appuser 10002 3854588 Aug 13 16:30 debug.log
-rw-r--r-- appuser 10002 52430839 Aug 12 13:48 debug.log.1
-rw-r--r-- appuser 10002 47803057 Aug 13 16:30 event.log
-rw-r--r-- appuser 10002 52439187 Aug 11 22:25 event.log.1
-rw-r--r-- appuser 10002 52446542 Aug 10 00:19 event.log.2
-rw-r--r-- appuser 10002 52443341 Aug 08 02:10 event.log.3
-rw-r--r-- appuser 10002 52431483 Aug 06 04:01 event.log.4
-rw-r--r-- appuser 10002 52445065 Aug 04 05:48 event.log.5
-rw-r--r-- appuser 10002 3917 Aug 13 04:55 kernel.log
-rw-r--r-- appuser 10002 1345359 Aug 13 16:12 system.log
developer-production-9f12f3i2ulk-solace-primary-0> enable
developer-production-9f12f3i2ulk-solace-primary-0# config
developer-production-9f12f3i2ulk-solace-primary-0(configure)# home
developer-production-9f12f3i2ulk-solace-primary-0> show queue *

Flags Legend:
I - Ingress Admin State (U=Up, D=Down)
E - Egress Admin State (U=Up, D=Down)
A - Access-Type (E=Exclusive, N=Non-Exclusive)
S - Selector (Y=Yes, N=No)
D - Durability (D=Durable, N=Non-Durable)
P - Priority (Y=Yes, N=No)

Queue Name Messages Spool Bind Status
Message VPN Spooled Usage (MB) HWM (MB) Count I E A S D P
-----
queue01
myservice 0 0.00 0.00 0 U U E N D N

developer-production-9f12f3i2ulk-solace-primary-0> █
```

```
mr-connection-gi45p3bocp.messaging.solace.cloud - PuTTY
developer-production-9f12f3i2ulk-solace-primary-0> show queue queue01 detail

Name : queue01
Message VPN : myservice
Durability : Durable
Id : 14
Admin Ingress : Up
Admin Egress : Up
Access Type : Exclusive
Partition Count : 0
Owner :
Created by mgmt : Yes
All Others Permission : Consume (1100)
Quota (MB) : 500
Respect Message Priority : No
Respect TTL : No
Max TTL (Seconds) : 0 (Disabled)
Well Known : Yes
Reject Msg to Sender on Discard : Yes
    Including When Shutdown : No
Bind Time Forwarding Mode : Store-And-Forward
Current Messages Spooled : 0
Current Spool Usage (MB) : 0.0000
High Water Mark (MB) : 0.0000
Total Delivered Unacked Msgs : 0
Max Delivered Unacked Msgs Per Flow : 10000
Total Acknowledgments In-Progress : 0
Redelivery : Enabled
    Max Redelivery : 0
    Redelivery Delay : Disabled
        Multiplier : 2.00
        Initial Interval (ms) : 1000
        Max Interval (ms) : 64000
```

Windows taskbar at the bottom shows: Search bar, taskbar icons (Edge, File Explorer, etc.), system tray with weather (28°C Mostly cloudy), language (ENG), and date/time (22:02 13-08-2023).