

## \*astTECS Voice Logger with ViciDial

1. Upload the "astVlogger.tar.gz" file to your webroot folder and untar the file.

```
[root@localhost html]# tar zxvf astVlogger.tar.gz
```

2. Change the owner and group of astVlogger folder to [apache](#)

```
[root@localhost html]# chown apache:apache astVlogger
```

3. Goto astVlogger folder and execute the [astVLogger.3.0.0](#) file.

```
[root@localhost astVlogger]# ./astVLogger.3.0.0
-bash: ./astVLogger.3.0.0: Permission denied
You have new mail in /var/spool/mail/root
[root@localhost astVlogger]# chmod 777 astVLogger.3.0.0
[root@localhost astVlogger]# ./astVLogger.3.0.0
mysqladmin: CREATE DATABASE failed; error: 'Can't create database 'voicellogger'; database exists'
Database Created
ERROR 1062 (23000) at line 41: Duplicate entry 'l-admin' for key 'id'
Updated database
mkdir: cannot create directory '/var/spool/asterisk/monitor/movedvoicefiles': File exists
Folder Created
Link created
PHP Warning: Invalid argument supplied for foreach() in /var/www/html/astVlogger/voicefilescopy.php on line 26
```

4. Create a symbolic link.

```
[root@localhost astVlogger]# ln -s /var/spool/asterisk/monitor/movedvoicefiles/ /var/www/html/astVlogger/asttecs/voicefiles
```

5. Goto [AST\\_CRON\\_audio\\_1\\_move\\_mix.pl](#) file and change the line as follows.

```
[root@localhost astVlogger]# vi /usr/share/astguiclient/AST_CRON_audio_1_move_mix.pl
```

Original: ``$soxmixin "$dir1/$INfile" "$dir1/$OUTfile" "$dir2/$ALLfile"`;`

Change to: ``$soxmixin "$dir1/$INfile" "$dir1/$OUTfile" "$dir2/GSM/$ALLfile"`;`

Note: If GSM folder is not there inside /var/spool/asterisk/monitorDONE, please create the same.

Eg: `mkdir /var/spool/asterisk/monitorDONE/GSM`

6. Add crontab entry as follows.

```
00,15,30,45 * * * * /usr/bin/php /var/www/html/astVlogger/voicefilescopy.php
```

## 7. Accessing the voice logger

Open your web browser type server **IP/astVlogger**

192.168.2.111/astVlogger/asttecs/manager\_login.php

**\*astTECS**

Username

Password

Submit

@2014 astVlogger version 3.0.0 \*astTECS

Note: Default user name and password is 'admin' later you can change this.

## 8. Once you logged in you can find your server's Hard Disk usage and number voice files etc.

**\*astTECS | Voice Logger**

STATUS VOICE FILES DOWNLOAD ACCOUNT LOGOUT

**HARD DISK DRIVE STATUS**

**HDD SPACE USAGE**  
Free Space : 422 GB  
Used Space : 2% / tmpfs 1.9 GB

**VOICEFILES**  
Number Of Voicefiles 2

**WARNING**  
No Warning

Free (99.1%) Used (0.9%)

@2014 astVlogger version 3.0.0 \*astTECS

## 9. Click on voice files you will get the option to Play. Delete and Download the voice files

**\*astTECS | Voice Logger**

STATUS VOICE FILES DOWNLOAD ACCOUNT LOGOUT

search by: Select like continue

DATE	TIME	SOURCE	DESTINATION	DURATION	PLAY	DELETE	DOWNLOAD
2014-09-10	15:03:20	8867473975	nidhin	01:56			
2014-09-04	15:05:41	6665	sreejith	00:08			

FIRST PREVIOUS [ 1 / 2 ] TOTAL 2 NEXT LAST

Note: [Quick Time plug](#) in need to install in order to play the file from the browser.

10. You can go for a bulk downloading of the voice file by clicking the Download tab

**\* astTECS | Voice Logger**

STATUS VOICE FILES **DOWNLOAD** ACCOUNT LOGOUT

**VOICEFILES DOWNLOAD**

From Date01-10-2013

To Date26-11-2014

Zip The File

Successfully Created !

DOWNLOAD FILE

@2014 astVlogger version 3.0.0 \*astTECS

11. You can create the log in user names by clicking on Account tab.

**\* astTECS | Voice Logger**

STATUS VOICE FILES DOWNLOAD **ACCOUNT** LOGOUT

Add

search by:select\_fieldlike

continue

USERNAME	PASSWORD	USERTYPE	EDIT	DELETE
admin	admin	admin		

FIRST PREVIOUS [ 1 / 1TOTAL1 ] NEXT LAST

show\_all

@2014 astVlogger version 3.0.0 \*astTECS