

Elven Island

```
enable
configure terminal
interface GigabitEthernet0/0
ip address 59.68.96.33 255.255.255.224
no shutdown
exit
ip dhcp pool Elven_Island
network 59.68.96.32 255.255.255.224
default-router 59.68.96.33
end
```

Domain of Holfort Royal Capital

```
enable
configure terminal
interface GigabitEthernet0/0
ip address 103.77.0.1 255.255.240.0
no shutdown
interface Serial0/2/0
ip address 20.0.0.1 255.255.255.252
no shutdown
interface Serial0/3/0
ip address 40.0.0.1 255.255.255.252
no shutdown
interface Serial0/3/1
ip address 30.0.0.1 255.255.255.252
no shutdown
interface Serial0/2/1
ip address 50.0.0.1 255.255.255.252
no shutdown
exit
router rip
version 2
no auto-summary
network 103.77.0.0
network 20.0.0.0
network 30.0.0.0
network 40.0.0.0
network 50.0.0.0
no auto-summary
exit
```

Domain of Redgrave

```
enable
configure terminal
interface GigabitEthernet0/0
ip address 103.77.16.1 255.255.252.0
no shutdown
interface Serial0/3/0
ip address 40.0.0.2 255.255.255.252
no shutdown
interface Serial0/3/1
```

```
ip address 60.0.0.1 255.255.255.252
no shutdown
exit
ip dhcp pool Redgrave
network 103.77.16.0 255.255.252.0
default-router 103.77.16.1
dns-server 103.77.19.254
exit
ip dhcp excluded-address 103.77.19.254 103.77.19.254
ip route 103.77.24.0 255.255.255.128 60.0.0.2
ip route 103.77.24.128 255.255.255.192 60.0.0.2
router rip
version 2
no auto-summary
network 103.77.16.0
network 40.0.0.0
no auto-summary
exit
```

Domain of Roseblade

```
enable
configure terminal
interface GigabitEthernet0/0
ip address 103.77.20.1 255.255.254.0
no shutdown
interface Serial0/3/1
ip address 30.0.0.2 255.255.255.252
no shutdown
exit
ip dhcp pool Roseblade
network 103.77.20.0 255.255.254.0
default-router 103.77.20.1
dns-server 103.77.19.254
exit
router rip
version 2
no auto-summary
network 103.77.20.0
network 30.0.0.0
no auto-summary
exit
```

Domain of Atlee

```
enable
configure terminal
interface GigabitEthernet0/0
ip address 103.77.22.1 255.255.254.0
no shutdown
exit
interface Serial0/2/0
ip address 20.0.0.2 255.255.255.252
no shutdown
interface Serial0/3/0
```

```
ip address 70.0.0.1 255.255.255.252
no shutdown
exit
ip dhcp pool Atlee
network 103.77.22.0 255.255.254.0
default-router 103.77.22.1
dns-server 103.77.19.254
exit
ip dhcp excluded-address 103.77.23.254 103.77.23.254
ip route 103.77.24.128 255.255.255.192 70.0.0.2
router rip
version 2
no auto-summary
network 103.77.22.0
network 20.0.0.0
no auto-summary
exit
```

Domain Bartford

```
enable
configure terminal
interface GigabitEthernet0/0
ip address 103.77.24.1 255.255.255.128
no shutdown
interface GigabitEthernet0/1
ip address 103.77.24.129 255.255.255.192
no shutdown
interface Serial0/2/1
ip address 50.0.0.2 255.255.255.252
no shutdown
interface Serial0/3/1
ip address 60.0.0.2 255.255.255.252
no shutdown
interface Serial0/3/0
ip address 70.0.0.2 255.255.255.252
no shutdown
exit
ip dhcp pool BartfordBarony
network 103.77.24.0 255.255.255.128
default-router 103.77.24.1
dns-server 103.77.19.254
exit
ip dhcp pool BartfordDutchy
network 103.77.24.128 255.255.255.192
default-router 103.77.24.129
dns-server 103.77.19.254
exit
ip dhcp excluded-address 103.77.24.190 103.77.24.190
ip route 103.77.16.0 255.255.252.0 60.0.0.1
router rip
version 2
no auto-summary
network 103.77.24.0
network 103.77.24.128
```

```
network 50.0.0.0  
no auto-summary  
exit
```