Bcps

0.94

Generated by Doxygen 1.8.9.1

Thu Oct 8 2015 22:50:48

Contents

1	Hier	archical	Index		1
	1.1	Class I	Hierarchy		1
2	Clas	s Index			9
	2.1	Class I	_ist		9
3	File	Index			11
	3.1	File Lis	st		11
4	Clas	s Docu	mentation	1	13
	4.1	BcpsBi	ranchObje	ect Class Reference	13
	4.2	BcpsBi	ranchStrat	tegy Class Reference	13
		4.2.1	Detailed	Description	14
		4.2.2	Construc	ctor & Destructor Documentation	14
			4.2.2.1	BcpsBranchStrategy	14
			4.2.2.2	BcpsBranchStrategy	15
			4.2.2.3	~BcpsBranchStrategy	15
		4.2.3	Member	Function Documentation	15
			4.2.3.1	clone	15
			4.2.3.2	getType	15
			4.2.3.3	setType	15
			4.2.3.4	setModel	15
			4.2.3.5	getNumBranchObjects	15
			4.2.3.6	clearBest	15
			4.2.3.7	createCandBranchObjects	15
			4.2.3.8	betterBranchObject	16
			4.2.3.9	bestBranchObject	16
		4.2.4	Member	Data Documentation	
			4.2.4.1	type	

iv CONTENTS

		4.2.4.2	model	16
		4.2.4.3	numBranchObjects	16
		4.2.4.4	branchObjects	16
		4.2.4.5	bestBranchObject	16
		4.2.4.6	bestChangeUp	17
		4.2.4.7	bestNumberUp	17
		4.2.4.8	bestChangeDown	17
		4.2.4.9	bestNumberDown	17
4.3	BcpsC	onstraint C	Class Reference	17
	4.3.1	Detailed	Description	17
	4.3.2	Construc	ctor & Destructor Documentation	18
		4.3.2.1	BcpsConstraint	18
		4.3.2.2	BcpsConstraint	18
		4.3.2.3	~BcpsConstraint	18
		4.3.2.4	BcpsConstraint	18
4.4	BcpsC	onstraintP	ool Class Reference	18
	4.4.1	Detailed	Description	19
	4.4.2	Member	Function Documentation	19
		4.4.2.1	getNumConstraints	19
		4.4.2.2	getConstraints	19
		4.4.2.3	getConstraint	19
4.5	BcpsF	ieldListMo	d< T > Struct Template Reference	19
	4.5.1	Detailed	Description	20
	4.5.2	Member	Data Documentation	20
		4.5.2.1	numModify	20
		4.5.2.2	posModify	20
4.6	BcpsN	lessage Cl	lass Reference	20
	4.6.1	Detailed	Description	20
4.7	BcpsN	lodel Class	s Reference	20
	4.7.1	Detailed	Description	21
	4.7.2	Member	Function Documentation	21
		4.7.2.1	getVariables	21
		4.7.2.2	getConstrints	22
		4.7.2.3	bcpsMessageHandler	22
		4.7.2.4	bcpsMessages	22
		4.7.2.5	encodeBcps	22
		4.7.2.6	decodeBcps	22

CONTENTS

	4.7.3	Member	Data Documentation
		4.7.3.1	constraints
		4.7.3.2	variables
		4.7.3.3	numCoreConstraints
		4.7.3.4	numCoreVariables
		4.7.3.5	bcpsMessageHandler
		4.7.3.6	bcpsMessages
4.8	BcpsN	odeDesc (Class Reference
	4.8.1	Detailed	Description
	4.8.2	Construc	tor & Destructor Documentation
		4.8.2.1	BcpsNodeDesc
		4.8.2.2	BcpsNodeDesc
		4.8.2.3	~BcpsNodeDesc
	4.8.3	Member	Function Documentation
		4.8.3.1	initToNull
		4.8.3.2	setVars
		4.8.3.3	assignVars
		4.8.3.4	setCons
		4.8.3.5	assignCons
		4.8.3.6	getVars
		4.8.3.7	getCons
		4.8.3.8	vars
		4.8.3.9	cons
		4.8.3.10	assignVarSoftBound
		4.8.3.11	setVarSoftBound
		4.8.3.12	assignVarHardBound
		4.8.3.13	setConSoftBound
		4.8.3.14	setVarHardBound
		4.8.3.15	setConHardBound
		4.8.3.16	appendAddedConstraints
		4.8.3.17	setAddedConstraints
		4.8.3.18	delConstraints
		4.8.3.19	addVariables
		4.8.3.20	delVariables
		4.8.3.21	encodeDblFieldMods
		4.8.3.22	encodeIntFieldMods
		4.8.3.23	encodeObjectMods

vi CONTENTS

	4.8.3.24	decodeDblFieldMods
	4.8.3.25	decodeIntFieldMods
	4.8.3.26	decodeObjectMods
	4.8.3.27	encodeBcps
	4.8.3.28	decodeBcps
4.8.4	Member	Data Documentation
	4.8.4.1	vars
	4.8.4.2	cons
BcpsOl	bject Class	s Reference
4.9.1	Detailed	Description
4.9.2	Construc	tor & Destructor Documentation
	4.9.2.1	BcpsObject
4.9.3	Member	Function Documentation
	4.9.3.1	operator=
	4.9.3.2	clone
	4.9.3.3	infeasibility
	4.9.3.4	feasibleRegion
	4.9.3.5	createBranchObject
	4.9.3.6	preferredNewFeasible
	4.9.3.7	notPreferredNewFeasible
	4.9.3.8	resetBounds
	4.9.3.9	boundBranch
	4.9.3.10	floorCeiling
	4.9.3.11	upEstimate
	4.9.3.12	downEstimate
	4.9.3.13	encodeBcpsObject
	4.9.3.14	decodeBcpsObject
	4.9.3.15	encode
	4.9.3.16	decode
4.9.4	Member	Data Documentation
	4.9.4.1	intType
	4.9.4.2	validRegion
	4.9.4.3	hashValue
	4.9.4.4	numInactive
	4.9.4.5	effectiveness
BcpsOl	bjectListM	od Struct Reference
4.10.1	Detailed	Description
	BcpsOl 4.9.1 4.9.2 4.9.3 4.9.4	4.8.3.25 4.8.3.26 4.8.3.27 4.8.3.28 4.8.4 Member 4.8.4.1 4.8.4.2 BcpsObject Class 4.9.1 Detailed 4.9.2 Construct 4.9.2.1 4.9.3 Member 4.9.3.1 4.9.3.2 4.9.3.3 4.9.3.4 4.9.3.5 4.9.3.6 4.9.3.7 4.9.3.8 4.9.3.9 4.9.3.10 4.9.3.11 4.9.3.12 4.9.3.13 4.9.3.14 4.9.3.15 4.9.3.16 4.9.3.16 4.9.4.1 4.9.4.2 4.9.4.3 4.9.4.5 BcpsObjectListM

CONTENTS vii

	4.10.2	Member	Data Documentation	 	36
		4.10.2.1	numRemove	 	36
		4.10.2.2	posRemove	 	36
		4.10.2.3	numAdd	 	36
		4.10.2.4	objects	 	36
		4.10.2.5	lbHard	 	36
4.11	BcpsOb	ojectPool (Class Reference	 	36
	4.11.1	Detailed	Description	 	37
	4.11.2	Construc	ctor & Destructor Documentation	 	37
		4.11.2.1	BcpsObjectPool	 	37
	4.11.3	Member	Function Documentation	 	37
		4.11.3.1	freeGuts	 	37
		4.11.3.2	clear	 	37
		4.11.3.3	getNumKnowledges	 	38
		4.11.3.4	hasKnowledge	 	38
		4.11.3.5	getObjects	 	38
		4.11.3.6	getObject	 	38
4.12	BcpsSc	olution Cla	ass Reference	 	38
	4.12.1	Detailed	Description	 	39
	4.12.2	Construc	ctor & Destructor Documentation	 	39
		4.12.2.1	BcpsSolution	 	39
		4.12.2.2	BcpsSolution	 	39
		4.12.2.3	BcpsSolution	 	40
		4.12.2.4	~BcpsSolution	 	40
	4.12.3	Member	Function Documentation	 	40
		4.12.3.1	getSize	 	40
		4.12.3.2	setSize	 	40
		4.12.3.3	selectNonzeros	 	40
		4.12.3.4	print	 	40
		4.12.3.5	encodeBcps	 	40
		4.12.3.6	decodeBcps	 	40
	4.12.4	Member	Data Documentation	 	40
		4.12.4.1	size	 	41
		4.12.4.2	objects	 	41
		4.12.4.3	values	 	41
		4.12.4.4	quality	 	41
4.13	BcpsSu	ubTree Cla	ass Reference	 	41

viii CONTENTS

	4.13.1	Detailed D	escription				 	 	 	 	 	. 41
4.14	BcpsTr	eeNode Cla	ss Referenc	ce			 	 	 	 	 	. 42
	4.14.1	Detailed D	escription				 	 	 	 	 	. 43
	4.14.2	Constructo	or & Destruc	tor Docu	mentatio	on	 	 	 	 	 	. 43
		4.14.2.1	BcpsTreeNo	ode			 	 	 	 	 	. 43
		4.14.2.2	\sim BcpsTreel	Node			 	 	 	 	 	. 43
	4.14.3	Member F	unction Doc	umentati	on		 	 	 	 	 	. 43
		4.14.3.1	generateCo	nstraints			 	 	 	 	 	. 43
		4.14.3.2	generateVa	riables .			 	 	 	 	 	. 43
		4.14.3.3	chooseBran	chingOb	ject		 	 	 	 	 	. 43
		4.14.3.4	installSubPr	oblem .			 	 	 	 	 	. 43
		4.14.3.5	handleBoun	dingStat	us		 	 	 	 	 	. 44
		4.14.3.6	process				 	 	 	 	 	. 44
		4.14.3.7	bound				 	 	 	 	 	. 44
		4.14.3.8	branch				 	 	 	 	 	. 44
		4.14.3.9	branchObje	ct			 	 	 	 	 	. 44
		4.14.3.10	setBranchO	bject			 	 	 	 	 	. 44
		4.14.3.11	encodeBcps	3			 	 	 	 	 	. 45
	4.14.4	Member D	ata Docume	entation .			 	 	 	 	 	. 45
		4.14.4.1	branchObje	ct			 	 	 	 	 	. 45
4.15	BcpsVa	ariable Clas	s Reference				 	 	 	 	 	. 45
	4.15.1	Detailed D	escription				 	 	 	 	 	. 45
	4.15.2	Constructo	or & Destruc	tor Docu	mentatio	on	 	 	 	 	 	. 45
		4.15.2.1	BcpsVariabl	е			 	 	 	 	 	. 45
		4.15.2.2	BcpsVariabl	e			 	 	 	 	 	. 46
		4.15.2.3	\sim BcpsVaria	ıble			 	 	 	 	 	. 46
		4.15.2.4	BcpsVariabl	e			 	 	 	 	 	. 46
4.16	BcpsVa	ariablePool (Class Refer	ence			 	 	 	 	 	. 46
	4.16.1	Detailed D	escription				 	 	 	 	 	. 46
	4.16.2	Member F	unction Doc	umentati	on		 	 	 	 	 	. 46
		4.16.2.1	getNumVari	ables			 	 	 	 	 	. 46
		4.16.2.2	getVariables	3			 	 	 	 	 	. 47
		4.16.2.3	getVariable				 	 	 	 	 	. 47
Index												49

Chapter 1

Hierarchical Index

1.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

2 Hierarchical Index

```
AlpsNodeSelectionBreadth [external]
  AlpsNodeSelectionDepth[external]
  AlpsNodeSelectionEstimate [external]
  AlpsNodeSelectionHybrid[external]
AlpsParameter[external]
AlpsParameterSet[external]
  AlpsParams[external]
AlpsPriorityQueue < T > [external]
AlpsPriorityQueue < AlpsSubTree * > [external]
AlpsPriorityQueue < AlpsTreeNode * > [external]
AlpsStrLess[external]
AlpsTimer[external]
AlpsTreeSelection [external]
  AlpsTreeSelectionBest[external]
  AlpsTreeSelectionBreadth [external]
  AlpsTreeSelectionDepth [external]
  AlpsTreeSelectionEstimate [external]
std::array< T >
std::auto ptr< T >
std::basic string < Char >
  std::string
  std::wstring
std::basic_string< char >
std::basic string< wchar t >
std::bitset< Bits >
BitVector128[external]
CoinAbsFltEq[external]
CoinArrayWithLength [external]
  CoinArbitraryArrayWithLength [external]
  CoinBigIndexArrayWithLength [external]
  CoinDoubleArrayWithLength [external]
  CoinFactorizationDoubleArrayWithLength[external]
  CoinFactorizationLongDoubleArrayWithLength [external]
  CoinIntArrayWithLength [external]
  CoinUnsignedIntArrayWithLength [external]
  CoinVoidStarArrayWithLength [external]
CoinBaseModel[external]
  CoinModel[external]
  CoinStructuredModel[external]
CoinBuild[external]
CoinDenseVector< T > [external]
CoinError[external]
CoinExternalVectorFirstGreater_2< class, class, class > [external]
CoinExternalVectorFirstGreater_3 < class, class, class, class > [external]
CoinExternalVectorFirstLess_2< class, class, class > [external]
CoinExternalVectorFirstLess 3< class, class, class, class > [external]
CoinFactorization [external]
CoinFileIOBase [external]
```

1.1 Class Hierarchy 3

```
CoinFileInput[external]
   CoinFileOutput[external]
CoinFirstAbsGreater 2< class, class > [external]
CoinFirstAbsGreater 3< class, class, class > [external]
CoinFirstAbsLess 2< class, class > [external]
CoinFirstAbsLess 3< class, class, class > [external]
CoinFirstGreater 2< class, class > [external]
CoinFirstGreater 3< class, class, class > [external]
CoinFirstLess 2< class, class > [external]
CoinFirstLess_3 < class, class, class > [external]
CoinLpIO::CoinHashLink[external]
CoinMpsIO::CoinHashLink[external]
CoinIndexedVector[external]
   CoinPartitionedVector[external]
CoinLpIO [external]
CoinMessageHandler[external]
CoinMessages [external]
  AlpsMessage [external]
  CoinMessage [external]
CoinModelHash [external]
CoinModelHash2[external]
CoinModelHashLink[external]
CoinModelInfo2[external]
CoinModelLink[external]
CoinModelLinkedList[external]
CoinModelTriple [external]
CoinMpsCardReader[external]
CoinMpsIO [external]
CoinOneMessage[external]
CoinOtherFactorization [external]
   CoinDenseFactorization [external]
   CoinOslFactorization[external]
   CoinSimpFactorization[external]
CoinPackedMatrix [external]
CoinPackedVectorBase [external]
   CoinPackedVector[external]
   CoinShallowPackedVector[external]
CoinPair< S, T > [external]
CoinParam [external]
CoinPrePostsolveMatrix [external]
  CoinPostsolveMatrix[external]
   CoinPresolveMatrix [external]
CoinPresolveAction[external]
  do_tighten_action[external]
  doubleton_action[external]
  drop_empty_cols_action[external]
  drop empty rows action[external]
  drop_zero_coefficients_action[external]
  dupcol action[external]
  duprow3_action[external]
  duprow action[external]
  forcing constraint action[external]
  gubrow action[external]
```

4 Hierarchical Index

```
implied_free_action[external]
   isolated constraint action[external]
   make fixed action[external]
   remove dual action[external]
   remove fixed action[external]
  slack doubleton action[external]
  slack singleton action[external]
  subst constraint action[external]
  tripleton action[external]
  twoxtwo_action[external]
   useless_constraint_action[external]
CoinPresolveMonitor[external]
CoinRational [external]
CoinRelFltEq[external]
CoinSearchTreeBase [external]
   CoinSearchTree < class > [external]
CoinSearchTreeCompareBest[external]
CoinSearchTreeCompareBreadth [external]
CoinSearchTreeCompareDepth [external]
CoinSearchTreeComparePreferred[external]
CoinSearchTreeManager[external]
CoinSet[external]
   CoinSosSet[external]
CoinSnapshot[external]
CoinThreadRandom[external]
CoinTimer[external]
CoinTreeNode [external]
CoinTreeSiblings[external]
CoinTriple < S, T, U > [external]
CoinWarmStart[external]
   CoinWarmStartBasis [external]
   CoinWarmStartDual[external]
   CoinWarmStartPrimalDual[external]
   CoinWarmStartVector < T > [external]
   CoinWarmStartVector< double > [external]
   CoinWarmStartVector < U > [external]
   CoinWarmStartVectorPair< T, U > [external]
CoinWarmStartDiff[external]
   CoinWarmStartBasisDiff[external]
   CoinWarmStartDualDiff[external]
   CoinWarmStartPrimalDualDiff[external]
   CoinWarmStartVectorDiff< T > [external]
   CoinWarmStartVectorDiff< double > [external]
   CoinWarmStartVectorDiff< U > [external]
   CoinWarmStartVectorPairDiff< T, U > [external]
CoinYacc[external]
std::complex
std::unordered multimap< K, T >::const iterator
std::set< K >::const iterator
std::multiset < K >::const iterator
std::unordered multiset< K >::const iterator
std::vector< T >::const_iterator
std::unordered set< K >::const iterator
std::basic string< Char >::const iterator
```

1.1 Class Hierarchy 5

```
std::string::const_iterator
std::wstring::const iterator
std::deque < T >::const iterator
std::list< T >::const iterator
std::forward list< T >::const iterator
std::map < K, T >::const_iterator
std::unordered map< K, T>::const iterator
std::multimap< K, T >::const iterator
std::multimap< K, T >::const reverse iterator
std::unordered_multimap< K, T >::const_reverse_iterator
std::set < K >::const_reverse_iterator
std::multiset< K >::const_reverse_iterator
std::unordered multiset < K >::const reverse iterator
std::vector< T >::const_reverse_iterator
std::unordered set< K >::const reverse iterator
std::basic_string< Char >::const_reverse_iterator
std::string::const_reverse_iterator
std::wstring::const_reverse_iterator
std::deque< T >::const reverse iterator
std::list< T >::const reverse iterator
std::forward list< T >::const reverse iterator
std::map < K, T >::const reverse iterator
std::unordered map < K, T >::const reverse iterator
DeletePtrObject[external]
std::deque< T >
dropped zero[external]
EKKHlink[external]
std::error_category
std::error_code
std::error_condition
std::exception
   std::bad alloc
   std::bad_cast
   std::bad exception
   std::bad_typeid
   std::ios base::failure
   std::logic error
       std::domain error
       std::invalid argument
       std::length error
       std::out_of_range
   std::runtime error
       std::overflow error
       std::range error
       std::underflow_error
FactorPointers [external]
std::forward_list< T >
std::ios base
   basic ios < char >
   basic_ios< wchar_t >
   std::basic ios
       basic_istream < char >
       basic istream< wchar t>
       basic ostream < char >
```

6 Hierarchical Index

```
basic_ostream< wchar_t >
       std::basic istream
          basic ifstream < char >
          basic ifstream< wchar t >
          basic_iostream< char >
          basic_iostream< wchar_t >
          basic istringstream < char >
          basic istringstream< wchar t >
          std::basic ifstream
              std::ifstream
              std::wifstream
          std::basic_iostream
              basic fstream < char >
              basic_fstream< wchar_t >
              basic stringstream < char >
              basic_stringstream< wchar_t >
              std::basic fstream
                 std::fstream
                 std::wfstream
              std::basic_stringstream
                 std::stringstream
                 std::wstringstream
          std::basic_istringstream
              std::istringstream
              std::wistringstream
          std::istream
          std::wistream
       std::basic_ostream
          basic_iostream< char >
          basic iostream< wchar t>
          basic_ofstream < char >
          basic ofstream< wchar t>
          basic_ostringstream< char >
          basic_ostringstream< wchar_t >
          std::basic_iostream
          std::basic ofstream
              std::ofstream
              std::wofstream
          std::basic_ostringstream
              std::ostringstream
              std::wostringstream
          std::ostream
          std::wostream
       std::ios
       std::wios
std::unordered_multimap< K, T >::iterator
std::deque< T >::iterator
std::unordered multiset< K >::iterator
std::set< K >::iterator
std::multimap< K, T >::iterator
std::map< K, T >::iterator
std::multiset< K >::iterator
std::forward list< T >::iterator
std::wstring::iterator
```

1.1 Class Hierarchy 7

```
std::unordered_set< K >::iterator
std::string::iterator
std::vector< T >::iterator
std::basic string< Char >::iterator
std::list< T >::iterator
std::unordered_map< K, T >::iterator
std::list< T >
std::map< K, T>
std::map < AlpsKnowledgeType, AlpsKnowledgePool * >
std::multimap< K, T >
std::multiset< K >
presolvehlink[external]
std::priority queue < T >
std::queue < T >
Coin::ReferencedObject[external]
std::string::reverse_iterator
std::multimap< K, T >::reverse_iterator
std::map < K, T >::reverse_iterator
std::vector< T >::reverse iterator
std::wstring::reverse iterator
std::basic string< Char >::reverse iterator
std::unordered_map< K, T >::reverse_iterator
std::list< T >::reverse iterator
std::unordered_multimap< K, T >::reverse_iterator
std::multiset < K > :: reverse\_iterator
std::deque< T >::reverse iterator
std::set< K >::reverse_iterator
std::forward_list< T >::reverse_iterator
std::unordered_set< K >::reverse_iterator
std::unordered_multiset< K >::reverse_iterator
std::set< K >
std::smart ptr< T >
Coin::SmartPtr< T > [external]
std::stack< T >
symrec[external]
std::system error
std::thread
TotalWorkload [external]
std::unique\_ptr\!<\mathsf{T}>
std::unordered map< K, T >
std::unordered_multimap< K, T >
std::unordered multiset< K >
std::unordered set< K >
std::valarray< T >
std::vector< T >
std::vector< AlpsKnowledge * >
std::vector< BcpsConstraint * >
std::vector< BcpsVariable *>
std::vector< double >
std::vector< std::pair< std::string, AlpsParameter > >
std::vector< std::string >
std::weak_ptr< T >
Κ
S
```

8 Hierarchical Index

T U

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

BcpsBranchObject
BcpsBranchObject contains the member data required when choosing branching entities and excut-
ing actual branching
BcpsBranchStrategy
Branching strategy specifies: (1) how to select a candidate set of branching objects (2) how to com-
pare two branching objects
BcpsConstraint
BcpsConstraintPool
BcpsFieldListMod< T >
This class contains modifications for a single std::vector <t> object</t>
BcpsMessage
BcpsModel 2
BcpsNodeDesc
For a given type, the objectVecStorage_structure holds the description
BcpsObject
A class for describing the objects that comprise a BCPS subproblem
BcpsObjectListMod
Here is the set of vectorMod_ objects that represent the list of objects of a particular type (either
in relative or explicit form)
BcpsObjectPool
Object pool is used to store objects
BcpsSolution
This class holds the solution objects
BcpsSubTree
This class is the data structure for storing a subtree within BCPS
BcpsTreeNode
This class contain the data for a BCPS search tree node
BcpsVariable
BcpsVariablePool

10 **Class Index**

Chapter 3

File Index

3.1 File List

Here is a list of all documented files with brief descriptions:

cps.h	??
cpsBranchObject.h	??
cpsBranchStrategy.h	??
cpsConfig.h	??
cpsInterface.h	??
cpsLicense.h	??
cpsMessage.h	??
cpsModel.h	??
cpsNodeDesc.h	??
cpsObject.h	
cpsObjectPool.h	??
cpsSolution.h	??
cpsSubTree.h	??
cpsTreeNode.h	??
onfig_bcps_default.h	
onfig default h	??

12 File Index

Chapter 4

Class Documentation

4.1 BcpsBranchObject Class Reference

BcpsBranchObject contains the member data required when choosing branching entities and excuting actual branching.

```
#include <BcpsBranchObject.h>
```

Collaboration diagram for BcpsBranchObject:

4.2 BcpsBranchStrategy Class Reference

Branching strategy specifies: (1) how to select a candidate set of branching objects (2) how to compare two branching objects.

```
#include <BcpsBranchStrategy.h>
```

Collaboration diagram for BcpsBranchStrategy:

Public Member Functions

• BcpsBranchStrategy ()

Default Constructor.

• BcpsBranchStrategy (BcpsModel *m)

Useful Constructor.

virtual ∼BcpsBranchStrategy ()

Destructor.

virtual BcpsBranchStrategy * clone () const =0

Clone a branch strategy.

• int getType ()

Get type.

void setType (int t)

Set type.

void setModel (BcpsModel *m)

Set model

virtual void clearBest (BcpsModel *model)

Clear branching strategy environment before starting a new round of selecting the best branch object.

virtual int createCandBranchObjects (int numPassesLeft, double ub)

Create a set of candidate branching objects.

virtual int betterBranchObject (BcpsBranchObject *b, BcpsBranchObject *bestSoFar)=0

Compare branching object thisOne to bestSoFar.

virtual BcpsBranchObject * bestBranchObject ()

Compare branching objects in branchObjects .

• int getNumBranchObjects ()

Set/get branching objects.

Protected Attributes

int type

Type of branching strategy.

BcpsModel * model

Pointer to model.

int numBranchObjects

Following members are used to store candidate branching objects.

BcpsBranchObject ** branchObjects

The set of candiate branching objects.

BcpsBranchObject * bestBranchObject_

Following members are used to store information about best branching object found so far.

double bestChangeUp_

Change up for best.

int bestNumberUp_

Number of infeasibilities for up.

double bestChangeDown_

Change down for best.

int bestNumberDown_

Number of infeasibilities for down.

4.2.1 Detailed Description

Branching strategy specifies: (1) how to select a candidate set of branching objects (2) how to compare two branching objects.

Definition at line 39 of file BcpsBranchStrategy.h.

4.2.2 Constructor & Destructor Documentation

4.2.2.1 BcpsBranchStrategy::BcpsBranchStrategy() [inline]

Default Constructor.

Definition at line 83 of file BcpsBranchStrategy.h.

```
4.2.2.2 BcpsBranchStrategy::BcpsBranchStrategy ( BcpsModel * m ) [inline]
Useful Constructor.
Definition at line 95 of file BcpsBranchStrategy.h.
4.2.2.3 virtual BcpsBranchStrategy::~BcpsBranchStrategy( ) [inline], [virtual]
Destructor.
Definition at line 107 of file BcpsBranchStrategy.h.
4.2.3
       Member Function Documentation
4.2.3.1 virtual BcpsBranchStrategy* BcpsBranchStrategy::clone( )const [pure virtual]
Clone a branch strategy.
4.2.3.2 int BcpsBranchStrategy::getType() [inline]
Get type.
Definition at line 118 of file BcpsBranchStrategy.h.
4.2.3.3 void BcpsBranchStrategy::setType(int t) [inline]
Set type.
Definition at line 121 of file BcpsBranchStrategy.h.
4.2.3.4 void BcpsBranchStrategy::setModel( BcpsModel * m ) [inline]
Set model.
Definition at line 124 of file BcpsBranchStrategy.h.
4.2.3.5 int BcpsBranchStrategy::getNumBranchObjects ( ) [inline]
Set/get branching objects.
Definition at line 128 of file BcpsBranchStrategy.h.
4.2.3.6 virtual void BcpsBranchStrategy::clearBest ( BcpsModel * model ) [inline], [virtual]
Clear branching strategy environment before starting a new round of selecting the best branch object.
Definition at line 138 of file BcpsBranchStrategy.h.
4.2.3.7 virtual int BcpsBranchStrategy::createCandBranchObjects (int numPassesLeft, double ub) [inline], [virtual]
Create a set of candidate branching objects.
```

Definition at line 147 of file BcpsBranchStrategy.h.

4.2.3.8 virtual int BcpsBranchStrategy::betterBranchObject (BcpsBranchObject * b, BcpsBranchObject * bestSoFar)[pure virtual]

Compare branching object thisOne to bestSoFar.

If thisOne is better than bestObject, return branching direction(1 or -1), otherwise return 0. If bestSorFar is NULL, then always return branching direction(1 or -1).

4.2.3.9 virtual BcpsBranchObject* BcpsBranchStrategy::bestBranchObject() [virtual]

Compare branching objects in branchObjects .

Return the index of the best branching object. Also, set branch direction in the best object.

4.2.4 Member Data Documentation

4.2.4.1 int BcpsBranchStrategy::type_ [protected]

Type of branching strategy.

Definition at line 48 of file BcpsBranchStrategy.h.

4.2.4.2 BcpsModel* BcpsBranchStrategy::model_ [protected]

Pointer to model.

Definition at line 51 of file BcpsBranchStrategy.h.

4.2.4.3 int BcpsBranchStrategy::numBranchObjects_ [protected]

Following members are used to store candidate branching objects.

NOTE: They are required to be cleared before starting another round of selecting. Number of candidate branching objects.

Definition at line 58 of file BcpsBranchStrategy.h.

4.2.4.4 BcpsBranchObject** **BcpsBranchStrategy::branchObjects_** [protected]

The set of candiate branching objects.

Definition at line 60 of file BcpsBranchStrategy.h.

4.2.4.5 BcpsBranchObject* **BcpsBranchStrategy::bestBranchObject** [protected]

Following members are used to store information about best branching object found so far.

NOTE: They are required to be cleared before starting another round of selecting. Best branching object found so far.

Definition at line 69 of file BcpsBranchStrategy.h.

4.2.4.6 double BcpsBranchStrategy::bestChangeUp_ [protected]

Change up for best.

Definition at line 71 of file BcpsBranchStrategy.h.

4.2.4.7 int BcpsBranchStrategy::bestNumberUp_ [protected]

Number of infeasibilities for up.

Definition at line 73 of file BcpsBranchStrategy.h.

4.2.4.8 double BcpsBranchStrategy::bestChangeDown_ [protected]

Change down for best.

Definition at line 75 of file BcpsBranchStrategy.h.

4.2.4.9 int BcpsBranchStrategy::bestNumberDown_ [protected]

Number of infeasibilities for down.

Definition at line 77 of file BcpsBranchStrategy.h.

The documentation for this class was generated from the following file:

· BcpsBranchStrategy.h

4.3 BcpsConstraint Class Reference

Inheritance diagram for BcpsConstraint:

Collaboration diagram for BcpsConstraint:

Public Member Functions

• BcpsConstraint ()

Default constructor.

• BcpsConstraint (double lbh, double ubh, double lbs, double ubs)

Useful constructor.

virtual ∼BcpsConstraint ()

Desctructor constructor.

BcpsConstraint (const BcpsConstraint &rhs)

Copy constructor.

Additional Inherited Members

4.3.1 Detailed Description

Definition at line 355 of file BcpsObject.h.

4.3.2 Constructor & Destructor Documentation

4.3.2.1 BcpsConstraint::BcpsConstraint() [inline]

Default constructor.

Definition at line 359 of file BcpsObject.h.

4.3.2.2 BcpsConstraint::BcpsConstraint (double lbh, double ubh, double lbs, double ubs) [inline]

Useful constructor.

Definition at line 362 of file BcpsObject.h.

4.3.2.3 virtual BcpsConstraint::~BcpsConstraint() [inline], [virtual]

Desctructor constructor.

Definition at line 368 of file BcpsObject.h.

4.3.2.4 BcpsConstraint::BcpsConstraint (const BcpsConstraint & rhs) [inline]

Copy constructor.

Definition at line 371 of file BcpsObject.h.

The documentation for this class was generated from the following file:

· BcpsObject.h

4.4 BcpsConstraintPool Class Reference

Inheritance diagram for BcpsConstraintPool:

Collaboration diagram for BcpsConstraintPool:

Public Member Functions

void addConstraint (BcpsConstraint *con)

Add a constraint to pool.

• void deleteConstraint (int k)

Delete constraint k from pool.

int getNumConstraints () const

Query how many constraints are in the pool.

const std::vector< AlpsKnowledge * > & getConstraints () const

Get the vector of constraints.

AlpsKnowledge * getConstraint (int k) const

Get a constraints.

4.4.1 Detailed Description

Definition at line 104 of file BcpsObjectPool.h.

4.4.2 Member Function Documentation

4.4.2.1 int BcpsConstraintPool::getNumConstraints () const [inline]

Query how many constraints are in the pool.

Definition at line 116 of file BcpsObjectPool.h.

4.4.2.2 const std::vector < Alps Knowledge *> & Bcps Constraint Pool::get Constraints () const [inline]

Get the vector of constraints.

Definition at line 119 of file BcpsObjectPool.h.

4.4.2.3 AlpsKnowledge* BcpsConstraintPool::getConstraint(int k) const [inline]

Get a constraints.

Definition at line 122 of file BcpsObjectPool.h.

The documentation for this class was generated from the following file:

· BcpsObjectPool.h

4.5 BcpsFieldListMod < T > Struct Template Reference

This class contains modifications for a single std::vector < T > object.

#include <BcpsNodeDesc.h>

Inheritance diagram for BcpsFieldListMod< T >:

Public Attributes

· bool relative

How the modification is stored, explicit means complete replacement, relative means relative to some other explicit object vector ("explicit" is a key word so we can't name the field that.)

· int numModify

The number of entries to be modified.

int * posModify

The positions to be modified.

• T * entries

Values.

4.5.1 Detailed Description

template < class T> struct BcpsFieldListMod < T>

This class contains modifications for a single std::vector<T> object.

Definition at line 39 of file BcpsNodeDesc.h.

4.5.2 Member Data Documentation

4.5.2.1 template < class T > int BcpsFieldListMod < T >::numModify

The number of entries to be modified.

Definition at line 47 of file BcpsNodeDesc.h.

4.5.2.2 template < class T > int * BcpsFieldListMod < T >::posModify

The positions to be modified.

Definition at line 50 of file BcpsNodeDesc.h.

The documentation for this struct was generated from the following file:

· BcpsNodeDesc.h

4.6 BcpsMessage Class Reference

Inheritance diagram for BcpsMessage:

Collaboration diagram for BcpsMessage:

Public Member Functions

Constructors etc

BcpsMessage (Language language=us_en)
 Constructor.

4.6.1 Detailed Description

Definition at line 43 of file BcpsMessage.h.

The documentation for this class was generated from the following file:

BcpsMessage.h

4.7 BcpsModel Class Reference

Inheritance diagram for BcpsModel:

Collaboration diagram for BcpsModel:

Public Member Functions

std::vector< BcpsVariable * > getVariables () const

Return list of variables.

std::vector < BcpsConstraint * > getConstrints () const

Return list of constraints.

• CoinMessageHandler * bcpsMessageHandler () const

Get the message handler.

CoinMessages bcpsMessages ()

Return messages.

• AlpsReturnStatus encodeBcps (AlpsEncoded *encoded) const

Pack Bcps portion of model into an encoded object.

• AlpsReturnStatus decodeBcps (AlpsEncoded &encoded)

Unpack Bcps portion of model from an encoded object.

std::vector< BcpsConstraint * > & getConstraints ()

Get variables and constraints.

void setConstraints (BcpsConstraint **con, int size)

Set variables and constraints.

Protected Attributes

std::vector< BcpsConstraint * > constraints_

Constraints input by users (before preprocessing).

std::vector< BcpsVariable * > variables_

Variables input by users (before preprocessing).

int numCoreConstraints_

Number of core constraints.

• int numCoreVariables_

Number of core variables.

CoinMessageHandler * bcpsMessageHandler_

Message handler.

CoinMessages bcpsMessages_

Bcps messages.

4.7.1 Detailed Description

Definition at line 40 of file BcpsModel.h.

4.7.2 Member Function Documentation

4.7.2.1 std::vector < BcpsVariable *> BcpsModel::getVariables () const [inline]

Return list of variables.

Definition at line 117 of file BcpsModel.h.

4.7.2.2 std::vector < BcpsConstraint *> BcpsModel::getConstrints() const [inline] Return list of constraints. Definition at line 120 of file BcpsModel.h. 4.7.2.3 CoinMessageHandler* BcpsModel::bcpsMessageHandler()const [inline] Get the message handler. Definition at line 123 of file BcpsModel.h. 4.7.2.4 CoinMessages BcpsModel::bcpsMessages () [inline] Return messages. Definition at line 127 of file BcpsModel.h. 4.7.2.5 AlpsReturnStatus BcpsModel::encodeBcps (AlpsEncoded * encoded) const Pack Bcps portion of model into an encoded object. 4.7.2.6 AlpsReturnStatus BcpsModel::decodeBcps (AlpsEncoded & encoded) Unpack Bcps portion of model from an encoded object. **Member Data Documentation** 4.7.3 **4.7.3.1 std::vector**<**BcpsConstraint***> **BcpsModel::constraints** [protected] Constraints input by users (before preprocessing). Definition at line 45 of file BcpsModel.h. **4.7.3.2 std::vector**<**BcpsVariable***> **BcpsModel::variables**_ [protected] Variables input by users (before preprocessing). Definition at line 48 of file BcpsModel.h. **4.7.3.3** int BcpsModel::numCoreConstraints_ [protected] Number of core constraints. By default, all input constraints are core. Definition at line 54 of file BcpsModel.h. **4.7.3.4** int BcpsModel::numCoreVariables_ [protected]

Number of core variables.

By default, all input variables are core.

Definition at line 57 of file BcpsModel.h.

4.7.3.5 CoinMessageHandler* BcpsModel::bcpsMessageHandler_ [protected]

Message handler.

Definition at line 60 of file BcpsModel.h.

4.7.3.6 CoinMessages BcpsModel::bcpsMessages_ [protected]

Bcps messages.

Definition at line 63 of file BcpsModel.h.

The documentation for this class was generated from the following file:

BcpsModel.h

4.8 BcpsNodeDesc Class Reference

For a given type, the objectVecStorage_ structure holds the description.

#include <BcpsNodeDesc.h>

Inheritance diagram for BcpsNodeDesc:

Collaboration diagram for BcpsNodeDesc:

Public Member Functions

• BcpsNodeDesc ()

Default constructor.

BcpsNodeDesc (BcpsModel *m)

Useful constructor.

virtual ∼BcpsNodeDesc ()

Destructor.

void initToNull ()

Initialize member data.

void setVars (int numRem, const int *posRem, int numAdd, const BcpsObject **objects, bool relvlh, int numvlh, const int *vlhp, const double *vlhe, bool relvuh, int numvuh, const int *vuhp, const double *vuhe, bool relvls, int numvls, const int *vlsp, const double *vlse, bool relvus, int numvus, const int *vusp, const double *vuse)

Set variable objects.

void assignVars (int numRem, int *&posRem, int numAdd, BcpsObject **&objects, bool relvlh, int numvlh, int *&vlhp, double *&vlhe, bool relvuh, int numvuh, int *&vuhp, double *&vuhe, bool relvls, int numvls, int *&vlsp, double *&vlse, bool relvus, int numvus, int *&vusp, double *&vuse)

Assign variable objects.

• void setCons (int numRem, const int *posRem, int numAdd, const BcpsObject **objects, bool relclh, int numclh, const int *clhp, const double *clhe, bool relcuh, int numcuh, const int *cuhp, const double *cuhe, bool relcls, int numcls, const int *clsp, const double *clse, bool relcus, int numcus, const int *cusp, const double *cuse)

Set constraint objects.

void assignCons (int numRem, int *&posRem, int numAdd, BcpsObject **&objects, bool relclh, int numclh, int
 *&clhp, double *&clhe, bool relcuh, int numcuh, int *&cuhp, double *&cuhe, bool relcls, int numcls, int *&clsp,
 double *&clse, bool relcus, int numcus, int *&cusp, double *&cuse)

Assign constraint objects.

BcpsObjectListMod * getVars () const

Get variable objects.

BcpsObjectListMod * getCons () const

Get constraint objects.

BcpsObjectListMod * vars ()

Accesss varaibles.

BcpsObjectListMod * cons ()

Accesss constraints.

void assignVarSoftBound (int numModSoftVarLB, int *&varLBi, double *&varLBv, int numModSoftVarUB, int *&varUBi, double *&varUBv)

Set variable soft bounds.

void setVarSoftBound (int numModSoftVarLB, const int *varLBi, const double *varLBv, int numModSoftVarUB, const int *varUBi, const double *varUBv)

Set variable soft bounds.

void assignVarHardBound (int numModHardVarLB, int *&varLBi, double *&varLBv, int numModHardVarUB, int *&varUBi, double *&varUBv)

Set variable hard bounds.

void setConSoftBound (int numModSoftConLB, const int *conLBi, const double *conLBv, int numModSoftConUB, const int *conUBi, const double *conUBv)

Set constraint soft bounds.

• void setVarHardBound (int numModHardVarLB, const int *varLBi, const double *varLBv, int numModHardVarUB, const int *varUBi, const double *varUBv)

Set variable hard bounds.

void setConHardBound (int numModHardConLB, const int *conLBi, const double *conLBv, int numModHard←
 ConUB, const int *conUBi, const double *conUBv)

Set constraint hard bounds.

void appendAddedConstraints (int numAdd, BcpsObject **addCons)

Recode the added constraints.

void setAddedConstraints (int numAdd, BcpsObject **addCons)

Recode the added constraints.

void delConstraints (int numDel, int *indices)

Record the constraints are deleted.

void addVariables (int numAdd, BcpsObject **addVars)

Record added variables.

void delVariables (int numDel, int *indices)

Record deleted variables.

AlpsReturnStatus encodeBcps (AlpsEncoded *encoded) const

Pack bcps node description into an encoded.

AlpsReturnStatus decodeBcps (AlpsEncoded &encoded)

Unpack bcps node description into an encoded.

Protected Member Functions

- AlpsReturnStatus encodeDblFieldMods (AlpsEncoded *encoded, BcpsFieldListMod< double > *field) const

 Pack a double field into an encoded object.
- AlpsReturnStatus encodeIntFieldMods (AlpsEncoded *encoded, BcpsFieldListMod< int > *field) const

 Pack a integer field into an encoded object.
- AlpsReturnStatus encodeObjectMods (AlpsEncoded *encoded, BcpsObjectListMod *objMod) const Pack object modifications to an encoded object.
- AlpsReturnStatus decodeDblFieldMods (AlpsEncoded &encoded, BcpsFieldListMod< double > *field)
 Unpack a double field from an encoded object.
- AlpsReturnStatus decodeIntFieldMods (AlpsEncoded &encoded, BcpsFieldListMod< int > *field)
 Unpack a integer field from an encoded object.
- AlpsReturnStatus decodeObjectMods (AlpsEncoded &encoded, BcpsObjectListMod *objMod)
 Unpack object modifications to an encoded object.

Protected Attributes

- BcpsObjectListMod * vars_ Variable objects.
 BcpsObjectListMod * cons_
- BcpsObjectListMod * cons_

Constraint objects.

4.8.1 Detailed Description

For a given type, the objectVecStorage_ structure holds the description.

This description is explicit if the numRemoved member is -1. In this case, the objects member holds the full list of objects of the given type. If an explicit description of the parent is given together with a relative description of the current node then the process of reconstructing the explicit description of the current node is as follows:

- 1. initialize the explicit list **L** to be the parent's list;
- 2. remove the objects on the indicated positions from L;
- modify the appropriate members of the objects in L according to the vectorMod_ members of the objectVec
 —
 Storage structure;
- 4. append the objects to be added to L.

If the numRemoved field is -1, that means that the current description is explicit. In this case, the contents of the vectorMod_ members are largely irrelevant, except for the relative fields which indicate whether the appropriate vectorMod_ member can ever be expressed as a relative description or not.

If the numRemoved field is >=0, then the current description is considered relative even if every vectorMod_member contains explicit data. The description of a node can be either explicit or relative to its parent. In the node there are a number of object types and for each object type the explicit/relative description is considered separately.

If the information on an object type is relative, it means that at least one of the fields (lbHard, ubHard, etc.) has a relative description.

Definition at line 128 of file BcpsNodeDesc.h.

4.8.2 Constructor & Destructor Documentation

4.8.2.1 BcpsNodeDesc::BcpsNodeDesc() [inline]

Default constructor.

Definition at line 141 of file BcpsNodeDesc.h.

4.8.2.2 BcpsNodeDesc::BcpsNodeDesc(BcpsModel*m) [inline]

Useful constructor.

Definition at line 144 of file BcpsNodeDesc.h.

4.8.2.3 virtual BcpsNodeDesc::∼**BcpsNodeDesc()** [virtual]

Destructor.

4.8.3 Member Function Documentation

4.8.3.1 void BcpsNodeDesc::initToNull()

Initialize member data.

4.8.3.2 void BcpsNodeDesc::setVars (int numRem, const int * posRem, int numAdd, const BcpsObject ** objects, bool relvlh, int numvlh, const int * vlhp, const double * vlhe, bool relvuh, int numvuh, const int * vuhp, const double * vuhe, bool relvlh, int numvus, const int * vusp, const double * vuse)

Set variable objects.

4.8.3.3 void BcpsNodeDesc::assignVars (int *numRem*, int *& *posRem*, int *numAdd*, BcpsObject **& *objects*, bool *relvIh*, int *numvIh*, int *& *vIhp*, double *& *vIhe*, bool *relvuh*, int numvuh, int *& *vuhp*, double *& *vuhe*, bool *relvIs*, int *numvIs*, int *& *vusp*, double *& *vuse*)

Assign variable objects.

Take over memory ownership.

4.8.3.4 void BcpsNodeDesc::setCons (int numRem, const int * posRem, int numAdd, const BcpsObject ** objects, bool relch, int numclh, const int * clhp, const double * clhe, bool relcuh, int numcuh, const int * cuhp, const double * cuhe, bool relcus, int numcus, const int * cusp, const double * cuse)

Set constraint objects.

4.8.3.5 void BcpsNodeDesc::assignCons (int numRem, int *& posRem, int numAdd, BcpsObject **& objects, bool relclh, int numclh, int *& clhp, double *& clhe, bool relcuh, int numcuh, int *& cuhp, double *& cuhe, bool relcls, int numcls, int *& cusp, double *& cuse)

Assign constraint objects.

Take over memory ownership.

4.8.3.6 BcpsObjectListMod* BcpsNodeDesc::getVars() const [inline]

Get variable objects.

Definition at line 243 of file BcpsNodeDesc.h.

4.8.3.7 BcpsObjectListMod* BcpsNodeDesc::getCons() const [inline]

Get constraint objects.

Definition at line 246 of file BcpsNodeDesc.h.

4.8.3.8 BcpsObjectListMod* BcpsNodeDesc::vars() [inline]

Accesss varaibles.

Definition at line 249 of file BcpsNodeDesc.h.

4.8.3.9 BcpsObjectListMod* BcpsNodeDesc::cons() [inline]

Accesss constraints.

Definition at line 252 of file BcpsNodeDesc.h.

4.8.3.10 void BcpsNodeDesc::assignVarSoftBound (int numModSoftVarLB, int *& varLBi, double *& varLBv, int numModSoftVarUB, int *& varUBi, double *& varUBv)

Set variable soft bounds.

Take ownerships of arraies.

4.8.3.11 void BcpsNodeDesc::setVarSoftBound (int numModSoftVarLB, const int * varLBi, const double * varLBv, int numModSoftVarUB, const int * varUBi, const double * varUBv)

Set variable soft bounds.

Don't take ownerships of arraies.

4.8.3.12 void BcpsNodeDesc::assignVarHardBound (int numModHardVarLB, int *& varLBi, double *& varLBv, int numModHardVarUB, int *& varUBi, double *& varUBv)

Set variable hard bounds.

Take ownerships of arraies.

4.8.3.13 void BcpsNodeDesc::setConSoftBound (int numModSoftConLB, const int * conLBi, const double * conLBv, int numModSoftConUB, const int * conUBi, const double * conUBv)

Set constraint soft bounds.

Don't take ownerships of arraies.

4.8.3.14 void BcpsNodeDesc::setVarHardBound (int numModHardVarLB, const int * varLBi, const double * varLBv, int numModHardVarUB, const int * varUBi, const double * varUBv)

Set variable hard bounds.

Don't take ownerships of arraies.

4.8.3.15 void BcpsNodeDesc::setConHardBound (int numModHardConLB, const int * conLBi, const double * conLBv, int numModHardConUB, const int * conUBi, const double * conUBv)

Set constraint hard bounds.

Don't take ownerships of arraies.

4.8.3.16 void BcpsNodeDesc::appendAddedConstraints (int numAdd, BcpsObject ** addCons) [inline]

Recode the added constraints.

Take over the memory ownship of aguments. Append to previous constraints.

Definition at line 304 of file BcpsNodeDesc.h.

4.8.3.17 void BcpsNodeDesc::setAddedConstraints (int numAdd, BcpsObject ** addCons) [inline]

Recode the added constraints.

Take over the memory ownship of aguments. Delete already added constraints.

Definition at line 323 of file BcpsNodeDesc.h.

4.8.3.18 void BcpsNodeDesc::delConstraints (int numDel, int * indices) [inline]

Record the constraints are deleted.

Take over the memory ownship of arguments.

Definition at line 337 of file BcpsNodeDesc.h.

4.8.3.19 void BcpsNodeDesc::addVariables (int numAdd, BcpsObject ** addVars) [inline]

Record added variables.

Take over the memory ownship of arguments.

Definition at line 344 of file BcpsNodeDesc.h.

4.8.3.20 void BcpsNodeDesc::delVariables (int numDel, int * indices) [inline]

Record deleted variables.

Take over the memory ownship of arguemnts.

Definition at line 357 of file BcpsNodeDesc.h.

4.8.3.21 AlpsReturnStatus BcpsNodeDesc::encodeDblFieldMods (AlpsEncoded * encoded, BcpsFieldListMod< double > * field) const [protected]

Pack a double field into an encoded object.

4.8.3.22 AlpsReturnStatus BcpsNodeDesc::encodeIntFieldMods (AlpsEncoded * encoded, BcpsFieldListMod< int > * field) const [protected]

Pack a integer field into an encoded object.

4.8.3.23 AlpsReturnStatus BcpsNodeDesc::encodeObjectMods (AlpsEncoded * encoded, BcpsObjectListMod * objMod) const [protected]

Pack object modifications to an encoded object.

4.8.3.24 AlpsReturnStatus BcpsNodeDesc::decodeDblFieldMods (AlpsEncoded & encoded, BcpsFieldListMod< double > * field) [protected]

Unpack a double field from an encoded object.

4.8.3.25 AlpsReturnStatus BcpsNodeDesc::decodeIntFieldMods (AlpsEncoded & encoded, BcpsFieldListMod < int > * field) [protected]

Unpack a integer field from an encoded object.

4.8.3.26 AlpsReturnStatus BcpsNodeDesc::decodeObjectMods (AlpsEncoded & encoded, BcpsObjectListMod * objMod) [protected]

Unpack object modifications to an encoded object.

4.8.3.27 AlpsReturnStatus BcpsNodeDesc::encodeBcps (AlpsEncoded * encoded) const

Pack bcps node description into an encoded.

4.8.3.28 AlpsReturnStatus BcpsNodeDesc::decodeBcps (AlpsEncoded & encoded)

Unpack bcps node description into an encoded.

- 4.8.4 Member Data Documentation
- **4.8.4.1 BcpsObjectListMod*** BcpsNodeDesc::vars_ [protected]

Variable objects.

Definition at line 133 of file BcpsNodeDesc.h.

4.8.4.2 BcpsObjectListMod* BcpsNodeDesc::cons_ [protected]

Constraint objects.

Definition at line 136 of file BcpsNodeDesc.h.

The documentation for this class was generated from the following file:

· BcpsNodeDesc.h

4.9 BcpsObject Class Reference

A class for describing the objects that comprise a BCPS subproblem.

```
#include <BcpsObject.h>
```

Inheritance diagram for BcpsObject:

Collaboration diagram for BcpsObject:

Public Member Functions

BcpsObject (const BcpsObject &rhs)

Copy constructor.

BcpsObject & operator= (const BcpsObject &rhs)

Assignment operator.

virtual BcpsObject * clone () const

Clone an enity.

• virtual double infeasibility (BcpsModel *m, int &preferredWay) const

Infeasibility of the object This is some measure of the infeasibility of the object.

virtual void feasibleRegion (BcpsModel *m)

Look at the current solution and set bounds to match the solution.

• virtual BcpsBranchObject * createBranchObject (BcpsModel *m, int way) const

Create a branching object and indicate which way to branch first.

virtual BcpsBranchObject * preferredNewFeasible (BcpsModel *m) const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a good direction.

virtual BcpsBranchObject * notPreferredNewFeasible (BcpsModel *m) const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

virtual void resetBounds (BcpsModel *m)

Reset variable bounds to their original values.

virtual bool boundBranch (BcpsModel *m) const

Return true if branches created by object will modify variable bounds.

virtual void floorCeiling (double &floorValue, double &ceilingValue, double value, double tolerance) const

Returns floor and ceiling i.e.

• virtual double upEstimate () const

Return "up" estimate.

• virtual double downEstimate () const

Return "down" estimate.

virtual AlpsReturnStatus encode (AlpsEncoded *encoded)

Pack into a encode object.

virtual AlpsKnowledge * decode (AlpsEncoded &encoded) const

Decode a constraint from an encoded object.

• int getObjectIndex () const

Return the value of the appropriate field.

void setObjectIndex (int ind)

Set the appropriate property.

virtual void hashing (BcpsModel *model=NULL)

Hashing.

Protected Member Functions

AlpsReturnStatus encodeBcpsObject (AlpsEncoded *encoded) const

Pack Bcps part to a encode object.

• AlpsReturnStatus decodeBcpsObject (AlpsEncoded &encoded)

Unpack Bcps part from a encode object.

Protected Attributes

int objectIndex

Global index of this object.

BcpsObjRep_t repType_

Core, indexed, or algorithmic.

BcpsIntegral_t intType_

The integrality type of the object, i.e., what values it can take up between the specified bounds.

BcpsValidRegion validRegion_

Valid in the whole tree or only the subtree rooted at the node that generate this object.

int status

The status of the object.

double lbHard

The lower bound of the object when it was first created.

• double ubHard_

The upper bound of the object when it was first created.

double lbSoft

The current lower bound of the object.

double ubSoft_

The current upper bound of the object.

double hashValue_

The hash value of this object.

int numInactive_

Number of inactive when in formulation.

• double effectiveness_

Effectiveness: nonnegative value.

4.9.1 Detailed Description

A class for describing the objects that comprise a BCPS subproblem.

At the BCPS level, all that is assumed about an object is that it has bounds and that it has an integrality type. The concept that an object

Definition at line 76 of file BcpsObject.h.

4.9.2 Constructor & Destructor Documentation

4.9.2.1 BcpsObject::BcpsObject (const BcpsObject & rhs) [inline]

Copy constructor.

Definition at line 159 of file BcpsObject.h.

4.9.3 Member Function Documentation

4.9.3.1 BcpsObject& BcpsObject::operator= (const BcpsObject & rhs)

Assignment operator.

```
4.9.3.2 virtual BcpsObject* BcpsObject::clone( ) const [inline], [virtual]
```

Clone an enity.

Definition at line 178 of file BcpsObject.h.

```
4.9.3.3 virtual double BcpsObject::infeasibility ( BcpsModel * m, int & preferredWay ) const [inline], [virtual]
```

Infeasibility of the object This is some measure of the infeasibility of the object.

It should be scaled to be in the range [0.0, 0.5], with 0.0 indicating the object is satisfied.

The preferred branching direction is returned in preferredWay,

This is used to prepare for strong branching but should also think of case when no strong branching

The object may also compute an estimate of cost of going "up" or "down". This will probably be based on pseudo-cost ideas.

Definition at line 231 of file BcpsObject.h.

```
4.9.3.4 virtual void BcpsObject::feasibleRegion ( BcpsModel * m ) [inline], [virtual]
```

Look at the current solution and set bounds to match the solution.

Definition at line 236 of file BcpsObject.h.

```
4.9.3.5 virtual BcpsBranchObject* BcpsObject::createBranchObject ( BcpsModel * m, int way ) const [inline], [virtual]
```

Create a branching object and indicate which way to branch first.

The branching object has to know how to create branches (fix variables, etc.)

Definition at line 241 of file BcpsObject.h.

```
4.9.3.6 virtual BcpsBranchObject* BcpsObject::preferredNewFeasible ( BcpsModel * m ) const [inline], [virtual]
```

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a good direction.

If the method cannot generate a feasible point (because there aren't any, or because it isn't bright enough to find one), it should return null.

Definition at line 252 of file BcpsObject.h.

```
4.9.3.7 virtual BcpsBranchObject* BcpsObject::notPreferredNewFeasible ( BcpsModel * m ) const [inline], [virtual]
```

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

If the method cannot generate a feasible point (because there aren't any, or because it isn't bright enough to find one), it should return null.

Definition at line 263 of file BcpsObject.h.

```
4.9.3.8 virtual void BcpsObject::resetBounds ( BcpsModel * m ) [inline], [virtual]
```

Reset variable bounds to their original values.

Bounds may be tightened, so it may be good to be able to reset them to their original values.

Definition at line 271 of file BcpsObject.h.

```
4.9.3.9 virtual bool BcpsObject::boundBranch ( BcpsModel * m ) const [inline], [virtual]
```

Return true if branches created by object will modify variable bounds.

Definition at line 275 of file BcpsObject.h.

4.9.3.10 virtual void BcpsObject::floorCeiling (double & floorValue, double & ceilingValue, double value, double tolerance) const [virtual]

Returns floor and ceiling i.e.

closest valid points.

```
4.9.3.11 virtual double BcpsObject::upEstimate() const [inline], [virtual]
```

Return "up" estimate.

Default: 1.0e-5.

Definition at line 284 of file BcpsObject.h.

4.9.3.12 virtual double BcpsObject::downEstimate() const [inline], [virtual]

Return "down" estimate.

Default: 1.0e-5.

Definition at line 287 of file BcpsObject.h.

4.9.3.13 AlpsReturnStatus BcpsObject::encodeBcpsObject (AlpsEncoded * encoded) const [inline], [protected]

Pack Bcps part to a encode object.

Definition at line 294 of file BcpsObject.h.

4.9.3.14 AlpsReturnStatus BcpsObject::decodeBcpsObject (AlpsEncoded & encoded) [inline], [protected]

Unpack Bcps part from a encode object.

Definition at line 310 of file BcpsObject.h.

4.9.3.15 virtual AlpsReturnStatus BcpsObject::encode (AlpsEncoded * encoded) [inline], [virtual]

Pack into a encode object.

Reimplemented from AlpsKnowledge.

Definition at line 331 of file BcpsObject.h.

4.9.3.16 virtual AlpsKnowledge* BcpsObject::decode(AlpsEncoded & encoded) const [inline], [virtual]

Decode a constraint from an encoded object.

Reimplemented from AlpsKnowledge.

Definition at line 338 of file BcpsObject.h.

4.9.4 Member Data Documentation

4.9.4.1 BcpsIntegral_t BcpsObject::intType [protected]

The integrality type of the object, i.e., what values it can take up between the specified bounds.

(Possible options: 'C' for continuous, 'I' for general integer, 'B' for binary and 'S' for semicontinuous)

Definition at line 90 of file BcpsObject.h.

4.9.4.2 BcpsValidRegion BcpsObject::validRegion_ [protected]

Valid in the whole tree or only the subtree rooted at the node that generate this object.

Definition at line 94 of file BcpsObject.h.

4.9.4.3 double BcpsObject::hashValue [protected]

The hash value of this object.

Definition at line 114 of file BcpsObject.h.

4.9.4.4 int BcpsObject::numInactive_ [protected]

Number of inactive when in formulation.

Definition at line 117 of file BcpsObject.h.

4.9.4.5 double BcpsObject::effectiveness_ [protected]

Effectiveness: nonnegative value.

Definition at line 120 of file BcpsObject.h.

The documentation for this class was generated from the following file:

· BcpsObject.h

4.10 BcpsObjectListMod Struct Reference

Here is the set of vectorMod_ objects that represent the list of objects of a particular type (either in relative or explicit form).

#include <BcpsNodeDesc.h>

Collaboration diagram for BcpsObjectListMod:

Public Attributes

• int numRemove

The number of entries to be deleted.

int * posRemove

The positions of the entries to be deleted.

• int numAdd

The number of objects that are to added.

BcpsObject ** objects

The objects to be added.

BcpsFieldListMod< double > lbHard

These are the data structures that store the changes in the individual fields.

4.10.1 Detailed Description

Here is the set of <code>vectorMod_</code> objects that represent the list of objects of a particular type (either in relative or explicit form).

If numRemove is positive, then posRemove contains the positions of the objects that are to be deleted from all the lists (that are stored relatively).

Definition at line 66 of file BcpsNodeDesc.h.

4.10.2 Member Data Documentation

4.10.2.1 int BcpsObjectListMod::numRemove

The number of entries to be deleted.

If this is -1, then all objects should be deleted, i.e., we have an explicit list.

Definition at line 70 of file BcpsNodeDesc.h.

4.10.2.2 int* BcpsObjectListMod::posRemove

The positions of the entries to be deleted.

Definition at line 73 of file BcpsNodeDesc.h.

4.10.2.3 int BcpsObjectListMod::numAdd

The number of objects that are to added.

Definition at line 76 of file BcpsNodeDesc.h.

4.10.2.4 BcpsObject** BcpsObjectListMod::objects

The objects to be added.

Definition at line 78 of file BcpsNodeDesc.h.

4.10.2.5 BcpsFieldListMod<double> BcpsObjectListMod::lbHard

These are the data structures that store the changes in the individual fields.

Definition at line 83 of file BcpsNodeDesc.h.

The documentation for this struct was generated from the following file:

· BcpsNodeDesc.h

4.11 BcpsObjectPool Class Reference

Object pool is used to store objects.

#include <BcpsObjectPool.h>

Inheritance diagram for BcpsObjectPool:

Collaboration diagram for BcpsObjectPool:

Public Member Functions

· BcpsObjectPool ()

Default construct.

• void freeGuts ()

Free object pointers.

• void clear ()

Reset to empty.

• virtual void addKnowledge (AlpsKnowledge *nk, double priority)

Add a knowledge to pool.

• virtual int getNumKnowledges () const

Query how many knowledges are in the pool.

• virtual std::pair< AlpsKnowledge *, double > getKnowledge () const

Query a knowledge, but doesn't remove it from the pool.

virtual bool hasKnowledge () const

Check whether the pool has knowledge.

void deleteObject (int k)

Delete object k from pool.

Get all objects.

AlpsKnowledge * getObject (int k) const

Get a object.

4.11.1 Detailed Description

Object pool is used to store objects.

Definition at line 36 of file BcpsObjectPool.h.

4.11.2 Constructor & Destructor Documentation

```
4.11.2.1 BcpsObjectPool::BcpsObjectPool( ) [inline]
```

Default construct.

Definition at line 45 of file BcpsObjectPool.h.

4.11.3 Member Function Documentation

```
4.11.3.1 void BcpsObjectPool::freeGuts() [inline]
```

Free object pointers.

Definition at line 53 of file BcpsObjectPool.h.

```
4.11.3.2 void BcpsObjectPool::clear( ) [inline]
```

Reset to empty.

Don't free memory.

Definition at line 61 of file BcpsObjectPool.h.

```
4.11.3.3 virtual int BcpsObjectPool::getNumKnowledges( )const [inline], [virtual]
```

Query how many knowledges are in the pool.

Implements AlpsKnowledgePool.

Definition at line 69 of file BcpsObjectPool.h.

```
4.11.3.4 virtual bool BcpsObjectPool::hasKnowledge() const [inline], [virtual]
```

Check whether the pool has knowledge.

Reimplemented from AlpsKnowledgePool.

Definition at line 79 of file BcpsObjectPool.h.

```
4.11.3.5 const std::vector<AlpsKnowledge *>& BcpsObjectPool::getObjects( ) const [inline]
```

Get all objects.

Definition at line 96 of file BcpsObjectPool.h.

```
4.11.3.6 AlpsKnowledge* BcpsObjectPool::getObject(int k) const [inline]
```

Get a object.

Definition at line 99 of file BcpsObjectPool.h.

The documentation for this class was generated from the following file:

· BcpsObjectPool.h

4.12 BcpsSolution Class Reference

This class holds the solution objects.

#include <BcpsSolution.h>

Inheritance diagram for BcpsSolution:

Collaboration diagram for BcpsSolution:

Public Member Functions

• BcpsSolution ()

Default constructor.

• BcpsSolution (int size, const double *values, double q)

Useful constructor.

BcpsSolution (int size, BcpsObject p *&objects, double *&values, double q)

Construct an object using the given arrays.

virtual ∼BcpsSolution ()

Distructor.

· virtual void print (std::ostream &os) const

Print out the solution.

AlpsReturnStatus encodeBcps (AlpsEncoded *encoded) const

Pack Bcps part of solution into an encoded objects.

AlpsReturnStatus decodeBcps (AlpsEncoded &encoded)

Unpack Bcps part of solution from an encoded objects.

• int getSize () const

Get the appropriate data member.

void setSize (int s)

Set/assign the appropriate data member.

virtual BcpsSolution * selectNonzeros (const double etol=1e-5) const

Select the fractional/nonzero elements from the solution array and return a new object in compacted form.

Protected Attributes

int size

Size of values_.

• BcpsObject_p * objects_

List of objects associated with values.

double * values_

Solution values.

double quality_

Quality/Objective value associated with this solution.

4.12.1 Detailed Description

This class holds the solution objects.

At this level, a solution is just considered to be a list of objects with associated values.

Definition at line 34 of file BcpsSolution.h.

4.12.2 Constructor & Destructor Documentation

```
4.12.2.1 BcpsSolution::BcpsSolution() [inline]
```

Default constructor.

Definition at line 58 of file BcpsSolution.h.

4.12.2.2 BcpsSolution::BcpsSolution (int size, const double * values, double q) [inline]

Useful constructor.

Definition at line 64 of file BcpsSolution.h.

4.12.2.3 BcpsSolution::BcpsSolution (int size, BcpsObject_p *& objects, double *& values, double q) [inline]

Construct an object using the given arrays.

Note that the new objects takes over the pointers and NULLs them out in the calling method.

Definition at line 80 of file BcpsSolution.h.

4.12.2.4 virtual BcpsSolution::~BcpsSolution() [inline], [virtual]

Distructor.

Definition at line 88 of file BcpsSolution.h.

4.12.3 Member Function Documentation

4.12.3.1 int BcpsSolution::getSize () const [inline]

Get the appropriate data member.

Definition at line 100 of file BcpsSolution.h.

4.12.3.2 void BcpsSolution::setSize(int s) [inline]

Set/assign the appropriate data member.

Definition at line 108 of file BcpsSolution.h.

4.12.3.3 virtual BcpsSolution* BcpsSolution::selectNonzeros (const double etol = 1e-5) const [virtual]

Select the fractional/nonzero elements from the solution array and return a new object in compacted form.

4.12.3.4 virtual void BcpsSolution::print (std::ostream & os) const [inline], [virtual]

Print out the solution.

Reimplemented from AlpsSolution.

Definition at line 130 of file BcpsSolution.h.

4.12.3.5 AlpsReturnStatus BcpsSolution::encodeBcps (AlpsEncoded * encoded) const

Pack Bcps part of solution into an encoded objects.

4.12.3.6 AlpsReturnStatus BcpsSolution::decodeBcps (AlpsEncoded & encoded)

Unpack Bcps part of solution from an encoded objects.

4.12.4 Member Data Documentation

4.12.4.1 int BcpsSolution::size_ [protected]

Size of values .

Definition at line 44 of file BcpsSolution.h.

4.12.4.2 BcpsObject_p* BcpsSolution::objects_ [protected]

List of objects associated with values.

Can be NULL.

Definition at line 47 of file BcpsSolution.h.

4.12.4.3 double* BcpsSolution::values_ [protected]

Solution values.

Definition at line 50 of file BcpsSolution.h.

4.12.4.4 double BcpsSolution::quality_ [protected]

Quality/Objective value associated with this solution.

Definition at line 53 of file BcpsSolution.h.

The documentation for this class was generated from the following file:

· BcpsSolution.h

4.13 BcpsSubTree Class Reference

This class is the data structure for storing a subtree within BCPS.

#include <BcpsSubTree.h>

Inheritance diagram for BcpsSubTree:

Collaboration diagram for BcpsSubTree:

4.13.1 Detailed Description

This class is the data structure for storing a subtree within BCPS.

The biggest addition to the fields that already exist withink ALPS is the storage for the global list of objects that are active within that subtree. Initally, this will be implemeted as a std::set, but later on should be changed to something more efficient such as a hash table or something like that.

Definition at line 42 of file BcpsSubTree.h.

The documentation for this class was generated from the following file:

BcpsSubTree.h

4.14 BcpsTreeNode Class Reference

This class contain the data for a BCPS search tree node.

#include <BcpsTreeNode.h>

Inheritance diagram for BcpsTreeNode:

Collaboration diagram for BcpsTreeNode:

Public Member Functions

BcpsTreeNode ()

Default constructor.

virtual ~BcpsTreeNode ()

Destructor.

virtual int process (bool isRoot=false, bool rampUp=false)

This methods performs the processing of the node.

virtual int bound (BcpsModel *model)=0

Bounding procedure to estimate quality of this node.

virtual std::vector< CoinTriple< AlpsNodeDesc *, AlpsNodeStatus, double >> branch ()=0

This method must be invoked on a pregnant node (which has all the information needed to create the children) and should create the children's decriptions.

const BcpsBranchObject * branchObject () const

Return the branching object.

void setBranchObject (BcpsBranchObject *b)

Set the branching object.

Protected Member Functions

virtual int generateConstraints (BcpsModel *model, BcpsConstraintPool *conPool)

Generate constraints.

virtual int generateVariables (BcpsModel *model, BcpsVariablePool *varPool)

Generate variables.

• virtual int chooseBranchingObject (BcpsModel *model)=0

Choose a branching object.

• virtual int installSubProblem (BcpsModel *model)=0

Extract node information (bounds, constraints, variables) from this node and load the information into the relaxation solver, such as linear programming solver.

virtual int handleBoundingStatus (int status, bool &keepOn, bool &fathomed)

Handle bounding status:

AlpsReturnStatus encodeBcps (AlpsEncoded *encoded) const

Pack Bcps portion of node into an encoded object.

Protected Attributes

• BcpsBranchObject * branchObject_

Branching object for this node, which has information of how to execute branching.

4.14.1 Detailed Description

This class contain the data for a BCPS search tree node.

At this level, we consider a tree node to be simply a list of objects. The objects are organized by type. A differencing scheme is implemented here by looking for differences between the lists of each type in the current node and its parent.

Definition at line 46 of file BcpsTreeNode.h.

4.14.2 Constructor & Destructor Documentation

```
4.14.2.1 BcpsTreeNode::BcpsTreeNode( ) [inline]
```

Default constructor.

Definition at line 99 of file BcpsTreeNode.h.

```
4.14.2.2 virtual BcpsTreeNode::~BcpsTreeNode( ) [inline], [virtual]
```

Destructor.

Definition at line 102 of file BcpsTreeNode.h.

4.14.3 Member Function Documentation

```
4.14.3.1 virtual int BcpsTreeNode::generateConstraints ( BcpsModel * model, BcpsConstraintPool * conPool ) [inline], [protected], [virtual]
```

Generate constraints.

The generated constraints are stored in constraint pool. The default implementation does nothing.

Definition at line 58 of file BcpsTreeNode.h.

```
4.14.3.2 virtual int BcpsTreeNode::generateVariables ( BcpsModel * model, BcpsVariablePool * varPool ) [inline], [protected], [virtual]
```

Generate variables.

The generated varaibles are stored in variable pool. The default implementation does nothing.

Definition at line 66 of file BcpsTreeNode.h.

```
4.14.3.3 virtual int BcpsTreeNode::chooseBranchingObject(BcpsModel * model) [protected], [pure virtual]
```

Choose a branching object.

```
4.14.3.4 virtual int BcpsTreeNode::installSubProblem ( BcpsModel * model ) [protected], [pure virtual]
```

Extract node information (bounds, constraints, variables) from this node and load the information into the relaxation solver, such as linear programming solver.

4.14.3.5 virtual int BcpsTreeNode::handleBoundingStatus (int *status*, bool & *keepOn*, bool & *fathomed*) [inline], [protected], [virtual]

Handle bounding status:

- · relaxed feasible but not integer feasible,
- · integer feasible,
- · infeasible,
- · unbounded.
- · fathomed (for instance, reaching objective limit for LP). Set node status accordingly.

Parameters

staus	Input The solution status of bounding.
keepOn	Output Whether to keep on bounding.
fathomed	Output Whether this node is fathomed.

Definition at line 91 of file BcpsTreeNode.h.

```
4.14.3.6 virtual int BcpsTreeNode::process (bool isRoot = false, bool rampUp = false) [virtual]
```

This methods performs the processing of the node.

For branch and bound, this would mean performing the bounding operation. The minimum requirement for this method is that it change the status to either internal or fathomed so the tree manager can deal with it afterwards. The status of the node when it begins processing will be active.

```
4.14.3.7 virtual int BcpsTreeNode::bound ( BcpsModel * model ) [pure virtual]
```

Bounding procedure to estimate quality of this node.

```
4.14.3.8 virtual std::vector < CoinTriple < AlpsNodeDesc*, AlpsNodeStatus, double > > BcpsTreeNode::branch ( ) [pure virtual]
```

This method must be invoked on a pregnant node (which has all the information needed to create the children) and should create the children's decriptions.

The stati of the children can be any of the ones process() can return.

```
4.14.3.9 const BcpsBranchObject* BcpsTreeNode::branchObject( ) const [inline]
```

Return the branching object.

Definition at line 123 of file BcpsTreeNode.h.

```
4.14.3.10 void BcpsTreeNode::setBranchObject ( BcpsBranchObject * b ) [inline]
```

Set the branching object.

Definition at line 126 of file BcpsTreeNode.h.

4.14.3.11 AlpsReturnStatus BcpsTreeNode::encodeBcps (AlpsEncoded * encoded) const [inline], [protected]

Pack Bcps portion of node into an encoded object.

Definition at line 131 of file BcpsTreeNode.h.

4.14.4 Member Data Documentation

4.14.4.1 BcpsBranchObject* **BcpsTreeNode**::branchObject_ [protected]

Branching object for this node, which has information of how to execute branching.

Definition at line 52 of file BcpsTreeNode.h.

The documentation for this class was generated from the following file:

BcpsTreeNode.h

4.15 BcpsVariable Class Reference

Inheritance diagram for BcpsVariable:

Collaboration diagram for BcpsVariable:

Public Member Functions

• BcpsVariable ()

Default constructor.

BcpsVariable (double lbh, double ubh, double lbs, double ubs)

Useful constructor.

• virtual ∼BcpsVariable ()

Destructor.

• BcpsVariable (const BcpsVariable &rhs)

Copy constructor.

Additional Inherited Members

4.15.1 Detailed Description

Definition at line 383 of file BcpsObject.h.

4.15.2 Constructor & Destructor Documentation

4.15.2.1 BcpsVariable::BcpsVariable() [inline]

Default constructor.

Definition at line 386 of file BcpsObject.h.

4.15.2.2 BcpsVariable::BcpsVariable (double lbh, double ubh, double lbs, double ubs) [inline]

Useful constructor.

Definition at line 389 of file BcpsObject.h.

4.15.2.3 virtual BcpsVariable::~BcpsVariable() [inline], [virtual]

Destructor.

Definition at line 395 of file BcpsObject.h.

4.15.2.4 BcpsVariable::BcpsVariable (const BcpsVariable & rhs) [inline]

Copy constructor.

Definition at line 398 of file BcpsObject.h.

The documentation for this class was generated from the following file:

· BcpsObject.h

4.16 BcpsVariablePool Class Reference

Inheritance diagram for BcpsVariablePool:

Collaboration diagram for BcpsVariablePool:

Public Member Functions

void addVariable (BcpsVariable *var)

Add a variable to pool.

void deleteVariable (int k)

Delete variable k from pool.

• int getNumVariables () const

Query how many variables are in the pool.

const std::vector< AlpsKnowledge * > & getVariables () const

Get the vector of variables.

• AlpsKnowledge * getVariable (int k) const

Get the vector of variables.

4.16.1 Detailed Description

Definition at line 127 of file BcpsObjectPool.h.

4.16.2 Member Function Documentation

4.16.2.1 int BcpsVariablePool::getNumVariables () const [inline]

Query how many variables are in the pool.

Definition at line 139 of file BcpsObjectPool.h.

4.16.2.2 const std::vector < AlpsKnowledge *>& BcpsVariablePool::getVariables () const [inline]

Get the vector of variables.

Definition at line 142 of file BcpsObjectPool.h.

4.16.2.3 AlpsKnowledge* BcpsVariablePool::getVariable(int k) const [inline]

Get the vector of variables.

Definition at line 145 of file BcpsObjectPool.h.

The documentation for this class was generated from the following file:

· BcpsObjectPool.h

File Documentation

Index

\sim BcpsBranchStrategy	setType, 15
BcpsBranchStrategy, 15	type_, 16
\sim BcpsConstraint	BcpsConstraint, 17
BcpsConstraint, 18	\sim BcpsConstraint, 18
\sim BcpsNodeDesc	BcpsConstraint, 18
BcpsNodeDesc, 26	BcpsConstraintPool, 18
\sim BcpsSolution	getConstraint, 19
BcpsSolution, 40	getConstraints, 19
\sim BcpsTreeNode	getNumConstraints, 19
BcpsTreeNode, 43	BcpsFieldListMod
~BcpsVariable	numModify, 20
BcpsVariable, 46	posModify, 20
•	BcpsFieldListMod< T >, 19
addVariables	BcpsMessage, 20
BcpsNodeDesc, 28	bcpsMessageHandler
appendAddedConstraints	BcpsModel, 22
BcpsNodeDesc, 28	bcpsMessageHandler_
assignCons	BcpsModel, 23
BcpsNodeDesc, 26	•
assignVarHardBound	bcpsMessages
BcpsNodeDesc, 27	BcpsModel, 22
assignVarSoftBound	bcpsMessages_
BcpsNodeDesc, 27	BcpsModel, 23
assignVars	BcpsModel, 20
BcpsNodeDesc, 26	bcpsMessageHandler, 22
	bcpsMessageHandler_, 23
BcpsBranchObject, 13	bcpsMessages, 22
BcpsBranchStrategy, 13	bcpsMessages_, 23
\sim BcpsBranchStrategy, 15	constraints_, 22
BcpsBranchStrategy, 14	decodeBcps, 22
bestBranchObject, 16	encodeBcps, 22
bestBranchObject_, 16	getConstrints, 21
bestChangeDown_, 17	getVariables, 21
bestChangeUp_, 16	numCoreConstraints_, 22
bestNumberDown_, 17	numCoreVariables_, 22
bestNumberUp_, 17	variables_, 22
betterBranchObject, 16	BcpsNodeDesc, 23
branchObjects_, 16	\sim BcpsNodeDesc, 26
clearBest, 15	addVariables, 28
clone, 15	appendAddedConstraints, 28
createCandBranchObjects, 15	assignCons, 26
getNumBranchObjects, 15	assignVarHardBound, 27
getType, 15	assignVarSoftBound, 27
model_, 16	assignVars, 26
numBranchObjects_, 16	BcpsNodeDesc, 26
setModel, 15	cons. 27

50 INDEX

cons_, 29	clear, 37
decodeBcps, 29	freeGuts, 37
decodeDblFieldMods, 29	getNumKnowledges, 37
decodeIntFieldMods, 29	getObject, 38
decodeObjectMods, 29	getObjects, 38
delConstraints, 28	hasKnowledge, 38
delVariables, 28	BcpsSolution, 38
encodeBcps, 29	\sim BcpsSolution, 40
encodeDblFieldMods, 28	BcpsSolution, 39
encodeIntFieldMods, 29	decodeBcps, 40
encodeObjectMods, 29	encodeBcps, 40
getCons, 27	getSize, 40
getVars, 26	objects_, 41
initToNull, 26	print, 40
setAddedConstraints, 28	quality_, 41
setConHardBound, 28	selectNonzeros, 40
setConSoftBound, 27	setSize, 40
setCons, 26	size_, 40
setVarHardBound, 27	values_, 41
setVarNoftBound, 27	BcpsSubTree, 41
setVars, 26	BcpsTreeNode, 42
vars, 27	~BcpsTreeNode, 43
vars_, 29	BcpsTreeNode, 43
BcpsObject, 30	bound, 44
BcpsObject, 32	branch, 44
boundBranch, 33	branch() 44
clone, 32	branchObject_, 45
createBranchObject, 32	chooseBranchingObject, 43
decode, 34	encodeBcps, 44
decodeBcpsObject, 34	generateConstraints, 43
downEstimate, 33	generateVariables, 43
effectiveness_, 35	handleBoundingStatus, 43
encode, 34	installSubProblem, 43
encodeBcpsObject, 34	process, 44
feasibleRegion, 32	setBranchObject, 44
floorCeiling, 33	BcpsVariable, 45
hashValue_, 34	~BcpsVariable, 46
infeasibility, 32	BcpsVariable, 45, 46
intType , 34	BcpsVariable, 45, 46 BcpsVariablePool, 46
notPreferredNewFeasible, 33	getNumVariables, 46
numInactive_, 35	getVariable, 47
operator=, 32	getVariables, 47
•	bestBranchObject
preferredNewFeasible, 33	BcpsBranchStrategy, 16
resetBounds, 33 upEstimate, 33	bestBranchObject
•	, -
validRegion_, 34	BcpsBranchStrategy, 16
BcpsObjectListMod, 35 IbHard, 36	bestChangeDown_
	BcpsBranchStrategy, 17
numAdd, 36	bestChangeUp_
numRemove, 36	BcpsBranchStrategy, 16
objects, 36	bestNumberDown_
posRemove, 36	BcpsBranchStrategy, 17
BcpsObjectPool, 36	bestNumberUp_
BcpsObjectPool, 37	BcpsBranchStrategy, 17

INDEX 51

betterBranchObject	effectiveness_
BcpsBranchStrategy, 16	BcpsObject, 35
bound	encode
BcpsTreeNode, 44	BcpsObject, 34
boundBranch	encodeBcps
BcpsObject, 33	BcpsModel, 22
branch	BcpsNodeDesc, 29
BcpsTreeNode, 44	BcpsSolution, 40
branchObject	BcpsTreeNode, 44
BcpsTreeNode, 44	encodeBcpsObject
branchObject_	BcpsObject, 34
BcpsTreeNode, 45	encodeDblFieldMods
branchObjects_	BcpsNodeDesc, 28
BcpsBranchStrategy, 16	encodeIntFieldMods
	BcpsNodeDesc, 29
chooseBranchingObject	encodeObjectMods
BcpsTreeNode, 43	BcpsNodeDesc, 29
clear	
BcpsObjectPool, 37	feasibleRegion
clearBest	BcpsObject, 32
BcpsBranchStrategy, 15	floorCeiling
clone	BcpsObject, 33
BcpsBranchStrategy, 15	freeGuts
BcpsObject, 32	BcpsObjectPool, 37
cons	
BcpsNodeDesc, 27	generateConstraints
cons_	BcpsTreeNode, 43
BcpsNodeDesc, 29	generateVariables
constraints_	BcpsTreeNode, 43
BcpsModel, 22	getCons
createBranchObject	BcpsNodeDesc, 27
BcpsObject, 32	getConstraint
createCandBranchObjects	BcpsConstraintPool, 19
BcpsBranchStrategy, 15	getConstraints
	BcpsConstraintPool, 19
decode	getConstrints
BcpsObject, 34	BcpsModel, 21
decodeBcps	getNumBranchObjects
BcpsModel, 22	BcpsBranchStrategy, 15
BcpsNodeDesc, 29	getNumConstraints
BcpsSolution, 40	BcpsConstraintPool, 19
decodeBcpsObject	getNumKnowledges
BcpsObject, 34	BcpsObjectPool, 37
decodeDblFieldMods	getNumVariables
BcpsNodeDesc, 29	BcpsVariablePool, 46
decodeIntFieldMods	getObject
BcpsNodeDesc, 29	BcpsObjectPool, 38
decodeObjectMods	getObjects
BcpsNodeDesc, 29	BcpsObjectPool, 38
delConstraints	getSize
BcpsNodeDesc, 28	BcpsSolution, 40
delVariables	getType
BcpsNodeDesc, 28	BcpsBranchStrategy, 15
downEstimate	getVariable
BcpsObject, 33	BcpsVariablePool, 47

52 INDEX

getVariables	preferredNewFeasible
BcpsModel, 21	BcpsObject, 33
BcpsVariablePool, 47	print
getVars	BcpsSolution, 40
BcpsNodeDesc, 26	process
•	BcpsTreeNode, 44
handleBoundingStatus	
BcpsTreeNode, 43	quality_
hasKnowledge	BcpsSolution, 41
BcpsObjectPool, 38	•
hashValue	resetBounds
BcpsObject, 34	BcpsObject, 33
infeasibility	selectNonzeros
BcpsObject, 32	BcpsSolution, 40
initToNull	setAddedConstraints
	BcpsNodeDesc, 28
BcpsNodeDesc, 26	setBranchObject
installSubProblem	BcpsTreeNode, 44
BcpsTreeNode, 43	setConHardBound
intType_	
BcpsObject, 34	BcpsNodeDesc, 28
	setConSoftBound
lbHard	BcpsNodeDesc, 27
BcpsObjectListMod, 36	setCons
	BcpsNodeDesc, 26
model_	setModel
BcpsBranchStrategy, 16	BcpsBranchStrategy, 15
	setSize
notPreferredNewFeasible	BcpsSolution, 40
BcpsObject, 33	setType
numAdd	• •
BcpsObjectListMod, 36	BcpsBranchStrategy, 15
numBranchObjects_	setVarHardBound
• —	BcpsNodeDesc, 27
BcpsBranchStrategy, 16	setVarSoftBound
numCoreConstraints_	BcpsNodeDesc, 27
BcpsModel, 22	setVars
numCoreVariables_	BcpsNodeDesc, 26
BcpsModel, 22	size_
numInactive_	BcpsSolution, 40
BcpsObject, 35	
numModify	type_
BcpsFieldListMod, 20	BcpsBranchStrategy, 16
numRemove	
BcpsObjectListMod, 36	upEstimate
DcpsObjectListiviou, 30	BcpsObject, 33
objects	• • •
BcpsObjectListMod, 36	validRegion_
•	BcpsObject, 34
objects_	values
BcpsSolution, 41	BcpsSolution, 41
operator=	variables_
BcpsObject, 32	
AA 186	BcpsModel, 22
posModify	vars
BcpsFieldListMod, 20	BcpsNodeDesc, 27
posRemove	vars_
BcpsObjectListMod, 36	BcpsNodeDesc, 29