




2. Configure IP address to routers in packet tracer. Explore the following messages: ping responses, destination unreachable, request timed out, reply




Router1
Physical
Config
CLI
IOS Command Line Interface
% Invalid input detected at '^' marker.
Router(config)#int fa0/0
Router(config-if)#ip address 10.0.0.1 255.255.255.0
Router(config-if)#no shut
Router(config-if)#exit
Router(config)#int fa0/1
Router(config-if)#ip address 20.0.0.1 255.255.255.0
Router(config-if)#no shut
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
Router(config-if)#exit
Router(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
Copy
Paste



Router0
Physical
Config
CLI
IOS Command Line Interface
Continue with configuration dialog? [yes/no]: n
Press RETURN to get started!
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip address 20.0.0.2 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if)#exit
Router(config)#int fa0/1
Router(config-if)#ip address 30.0.0.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
Router(config-if)#exit
Router(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
Copy
Paste


Router2
Physical
Config
CLI
IOS Command Line Interface
Continue with configuration dialog? [yes/no]: n
Press RETURN to get started!
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip address 30.0.0.2 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if)#exit
Router(config)#ip fa0/1
^
% Invalid input detected at '^' marker.
Router(config)#int fa0/1
Router(config-if)#ip address 40.0.0.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
Router(config-if)#exit
Router(config)#
Copy
Paste


PC0
Physical
Config
Desktop
Custom Interface
Command Prompt
X
Packet Tracer PC Command Line 1.0
PC>pin g 10.0.0.1
Invalid Command.
PC>ping 10.0.0.1
Pinging 10.0.0.1 with 32 bytes of data:
Reply from 10.0.0.1: bytes=32 time=0ms TTL=255
Reply from 10.0.0.1: bytes=32 time=0ms TTL=255
Reply from 10.0.0.1: bytes=32 time=0ms TTL=255
Reply from 10.0.0.1: bytes=32 time=0ms TTL=255
Ping statistics for 10.0.0.1:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms
PC>ping 20.0.0.2
Pinging 20.0.0.2 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 20.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
PC>ping 40.0.0.10
Pinging 40.0.0.10 with 32 bytes of data:
Reply from 10.0.0.1: Destination host unreachable.
Reply from 10.0.0.1: Destination host unreachable.
Reply from 10.0.0.1: Destination host unreachable.
Reply from 10.0.0.1: Destination host unreachable.
Ping statistics for 40.0.0.10:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
PC>

2) Configure IP address to routers in packet tracer. Explore the following messages: ping response, destination unreachable, request timed out, reply.

Step 1: Create a topology like this. Configure IP address and gateway to the hosts.



Step 2: Configure Interface IP address to Router. Click on Router R1, then click on CLI (Command Line Interface). You will see like this, "Continue with configuration dialog? [yes/no]:". Give "no" and Press Enter. Now you will go to user mode, now give "enable" and press enter to get into global configuration mode.

Step 3: Now configure router interface with ip address and subnet mask then give no shutdown to make this interface and line protocol up (i.e. Carefully configure ip address with proper interfaces in this

case fa 0/0 and fa 0/1, f is short form of fastethernet

Step 4: Now lights on all ports become green from red. Now open cmd of PC and check for Ping messages, Destination reachable, request time out and Reply.

Output:

PC > ping 10.0.0.1
Pinging 10.0.0.1 with 32 bytes of data:
Reply from 10.0.0.1: bytes=32 time=0ms TTL=255
Reply from 10.0.0.1: bytes=32 time=0ms TTL=255
Reply from 10.0.0.1: bytes=32 time=0ms TTL=255

Ping statistics for 10.0.0.1:
Packets: Sent = 4, Received = 4, Lost=0 (0% Loss)
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms

PC > ping 20.0.0.2
Pinging 20.0.0.2 with 32 bytes of data:
Request timed out.
Reque timed out.

Ping statistics for 20.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss)

PC > Ping 40.0.0.10
Pinging 40.0.0.10 with 32 bytes of data:

Bafna Gold
Date: Page:

Reply from 10.0.0.1: Destination host unreachable.
Reply from 10.0.0.1: Destination host unreachable.

Ping statistics for 40.0.0.10:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss)

10/10
28/9/26