

备餐计划 • Prep plan

24 Xpress App • 咖啡馆员工 • Café staff (BR26) • App 2026-10-04.145

备餐计划告诉你**今天或明天，每样熟食在每个时段要准备几份**，不用再凭感觉。

The prep plan tells you **how many of each cooked food to have ready in each time slot, today or tomorrow**, so you no longer guess.

截图里的**红框和箭头**是要看、要按的地方，红色数字对应下面的步骤。截图是 App 的英文画面，中文画面位置一样。

1

Red boxes and arrows show where to look and tap; the red numbers match the steps. The pictures show the English screens; the Chinese screens look the same.

首页 → 货品与库存 → 备餐计划

Home → Goods & stock → Prep plan

1

在首页「功能」往下滑到 **货品与库存**，按 **备餐计划**。

On Home, scroll the functions down to **Goods & stock** and tap **Prep plan**.

2

只有设定了备餐计划的店（现在是 BR26）才看得到这个按钮。

Only stores set up for the prep plan (now BR26) see this button.



每一行一样食物，每一格一个时段

One row per food, one column per time slot

1 上面选 **今天** 或 **明天**。开店前看今天，下班前看明天，方便先解冻、先备料。

Pick **Today** or **Tomorrow** at the top. Check today before opening and tomorrow before you go home, so you can thaw and prepare ahead.

2 每一格是那个时段要**准备好的**份数。时段：开店到 10 点 (≤ 10)、10-12、12-14、14-17、17-20、20 点后 (20-24)。最右边 **Day** 是全天合计。「·」表示那个时段不用准备。

Each cell is how many to **have ready** in that slot. Slots: opening to 10:00 (≤ 10), 10-12, 12-14, 14-17, 17-20, after 20:00 (20-24). **Day** on the right is the day total. "·" means nothing is needed in that slot.


3 卖得最多的排在最上面。

The best sellers are at the top.

例子 • Example

ODEN STICK: ≤ 10 要 4 支, 10-12 要 10 支, 12-14 要 5 支, 14-17 要 13 支, 17-20 要 2 支, 全天 34 支。

ODEN STICK: 4 by 10:00, 10 for 10-12, 5 for 12-14, 13 for 14-17, 2 for 17-20; 34 for the day.



只看要准备的食物，或显示全部

Food to prepare only, or show everything

- 1 平时表上只有要动手准备的食物（熟食、面碗、套餐碗）。包装好的饮料、零食不用准备，所以不显示。


Normally the table shows only food you have to prepare (cooked food, noodle bowls, combo bowls). Packaged drinks and snacks need no prep, so they are hidden.

- 2 想看全部，按最下面

显示全部商品（包括包装货）；再按

只显示要准备的食物 就回去。

To see everything, tap **Show all items (incl. packaged)** at the bottom; tap **Only food to prepare** to go back.



按收银机过去 4 个星期的销售算

Worked out from the last 4 weeks of till sales

- 1 App 看过去 4 个同一个星期几（例如今天星期二，就看前 4 个星期二），每个钟头平均卖了几份，加起来再往上进位。

The App looks at the last 4 **same weekdays** (on a Tuesday, the 4 previous Tuesdays), takes the average sold per hour, adds the hours up and **rounds up**.

2

卖完的时段数字会偏少：那天卖完了，收银机就没有记录。常常卖完的东西，请按经验多备一点。

Slots where it sold out read low: once it sold out, the till recorded nothing more. For items that often sell out, prepare a little more from experience.

3

公共假期、活动、下雨天，客人会多或少，数字只是参考，店长可以调整。

Public holidays, events and rain change the crowd; the numbers are a guide and the manager can adjust.

4

显示「这一天通常没有营业」：过去 4 个同一天都没有销售。显示「还没有这间店的每小时销售资料」：请告诉 HQ。

"Usually closed on this day": no sales on the last 4 same weekdays. "No hourly sales for this store yet": tell HQ.

© HQ • SETTINGS

加门店、改要显示的类别

Add stores, change the categories shown

1

HQ 在「我的 → 设定」改 **备餐计划的门店**（例如 BR26,BR24），那间店的员工就会看到按钮。

HQ changes **Stores with a prep plan** under Me → Settings (e.g. BR26,BR24); staff at those stores then see the button.

2

备餐计划要显示的类别：AutoCount 类别编号，默认 32 熟食、19 面碗、27 套餐碗。

Categories shown in the prep plan: AutoCount category codes, default 32 prepared food, 19 noodle bowl, 27 combo bowl.