

INDUSTRY KICK

PHASE-LOCKED INDUSTRIAL KICK INSTRUMENT

User Manual / Version 0.7.0

VST3 per Windows • 50 factory presets • 20 convolution spaces

WAV export PCM24 • Factory peak target -7 dBFS

909VOLTS

READY-TO-HIT / SUB-PROTECTED / TRUE CONVOLUTION

A MIX-READY KICK IN UNDER ONE MINUTE

RECOMMENDED WORKFLOW

1 CHOOSE THE CORE

Start with Round, Punch, Hard, Industrial or Rave. This is the main tonal decision.

2 SET TUNE

Tune the fundamental to the key of the track. The sub remains mono and phase-locked.

3 SET BODY / PUNCH / LENGTH

Use small moves to define weight, attack and duration without building a technical chain.

4 ADD CHARACTER

Drive, Colour and Metal work mainly above the protected sub range.

5 CHOOSE A SPACE

Open the IR browser, choose a chamber, then set Reverb, Decay and Width.

6 REFINE AND EXPORT

Use the four Mix macros, check the meter and drag DRAG / WAV into the DAW.

GAIN STAGING / -7 DBFS

-7 dBFS PEAK

This is the target for the factory presets. It is not too low: it leaves room for bass, synths, bus processing and mastering.

Do not confuse peak and RMS. A soft kick may have lower RMS but more punch; an industrial kick may be denser while reaching the same peak.

If more level is needed, raise Output by up to +6 dB. The final -0.8 dBFS ceiling prevents digital overs, but it does not replace proper mix gain staging.

PRACTICAL RULE

Choose a sound for its character, then level-match it in the DAW. Do not choose a preset only because it sounds louder.

INTERFACE MAP



SECTIONS

- 1 CORE**
Kick source and shape.
- 2 CHARACTER**
Protected distortion and tone.
- 3 SPACE**
Stereo convolution and ambience.
- 4 MIX CONTROL**
Four balance macros.
- 5 KICK LAB**
Shape, Evolve and Destroy transforms.
- 6 OUTPUT**
Trigger, meter, clipper and export.


THE KICK ENGINE



ESSENTIAL CONTROLS

- Tune - fundamental frequency in Hz; use it as the tuning reference.
- Body - weight and sustain of the synthesised body.
- Punch - energy and perceived duration of the transient.
- Length - total kick envelope in milliseconds.
- Core Type - changes the actual waveform and harmonic profile.

FIVE CORES / FIVE FAMILIES



AGGRESSIVE COLOUR, PROTECTED SUB



WHAT THE MACROS DO

- Drive: progressive saturation and hardening.
- Colour: changes harmonic balance and presence.
- Metal: industrial resonances and texture above the low end.
- Impact Monitor: slow hold for a clear view of a single kick.

INTERNAL DSP PATH



The sub is not simply boosted: it is split, kept coherent and recombined after the colour stage. Character can therefore become obvious without making the fundamental wobble or lose focus.

20 CONVOLUTION SPACES



BROWSER IR

TIGHT

Airlock
Booth
Drum Cell
Concrete Box
Short Plate

ROOMS

Studio
Concrete Room
Stone Chamber
Warehouse
Hangar

PASSAGES

Corridor
Tunnel
Sewer
Service Shaft
Underground

METAL / EXTREME

Steel Plate
Oil Tank
Container
Reactor
Abyss

RECOMMENDED USE

- Reverb sets the level of the parallel wet path.
- Decay shortens or lengthens the IR response.
- Width opens only the spatial layer; the sub remains mono.
- The wet path is filtered and ducked by the dry impact.
- For a mix-ready kick, start with 10% to 35% Reverb.

FOUR MUSICAL MACROS



WHAT ACTUALLY CHANGES

- SUB** Fundamental and weight below the crossover region.
- IMPACT** Attack, punch and front-of-speaker presence.
- SPACE** Level of the already-ducked convolution tail.
- GRIT** Density of the Character path above the sub.

THREE QUICK RECIPES

CLEAN CLUB

SUB 0.78
IMPACT 0.70
SPACE 0.18
GRIT 0.12

WAREHOUSE

SUB 0.74
IMPACT 0.76
SPACE 0.48
GRIT 0.42

INDUSTRIAL BLOCK

SUB 0.82
IMPACT 0.82
SPACE 0.32
GRIT 0.72

SHAPE / EVOLVE / DESTROY



SHAPE



SHAPE

Refines body, punch and contour. It is the safest control for moving a preset towards the mix.

EVOLVE



EVOLVE

Introduces tonal variation within the same family without modulating the fundamental. The sub does not wobble.

DESTROY



DESTROY

Increases clipping, harmonics and density above the protected sub. It does not randomise visible parameters.

LEVEL, CLIPPER AND WAV



FINAL STAGE

- TRIGGER: manual audition without creating a MIDI clip.
- OUTPUT: user trim from -18 to +6 dB after the factory target.
- METER L/R: output peak display with a readable hold time.
- CLIPPER: increases density and controls peaks before the trim.
- DRAG / WAV: 48 kHz PCM24 stereo render that can be dragged into the DAW.

READING THE LEVEL

FACTORY -7 dBFS

Factory preset reference: useful mix headroom with no need to normalise to 0 dBFS.

SAFETY -0.8 dBFS

Final technical ceiling. If it is active too often, lower Output or Clipper for a more open and less fatiguing sound.

50 PRESETS AND FAST EXPLORATION


FACTORY BANK

- 10 Deep Techno / Round
- 10 Hardgroove / Punch
- 10 Hard Techno / Hard
- 10 Industrial Techno / Industrial
- 10 Rave Techno / Rave
- Use - / + to step through factory and user presets without opening the bank.
- RANDOMIZER creates a new safe parameter combination and keeps Output at 0 dB.

USER PRESETS

- SAVE stores the current state under a user-defined name.
- Saved presets appear in the same browser after the factory bank.
- Use Undo and Redo while refining a sound.
- Use DRAG / WAV only when the kick is ready to commit.

SAFE EXPLORATION WORKFLOW



Randomizer stays inside musical ranges, keeps phase reset active and protects the sub. Treat the result as a starting point, then make small macro moves and verify it in the track before exporting.

INSTALLATION AND TROUBLESHOOTING

WINDOWS / ABLETON LIVE

- 1 STEP 1**
Close Ableton Live completely.
- 2 STEP 2**
Run the installer as administrator.
- 3 STEP 3**
Use C:\Program Files\Common Files\VST3.
- 4 STEP 4**
Reopen Live and start a VST3 rescan.
- 5 STEP 5**
Send a MIDI note; velocity 100-127 is a good starting point.

IF SOMETHING DOES NOT WORK

- Installer cannot write: Live is using the old VST3; close it in Task Manager.
- Plugin is missing: check the VST3 path and force a full rescan.
- No sound: use a MIDI track, arm it and check the routing.
- Tail is too long: lower Reverb or Decay; try a Tight IR.
- Kick is too loud: return Output to 0 dB and lower Clipper.

REQUIREMENTS AND COMPATIBILITY

- Windows 10/11 x64 and a 64-bit VST3 host.
- The bundle keeps the internal identifier of the original KICKCRAFTER for compatibility.
- The development installer is not digitally signed yet.
- For useful reports, send dry/default/stress WAV files, BPM, velocity and waveform/meter screenshots.

COMMERCIAL USE AND DELIVERY

PLUGIN LICENCE

- The licence grants use of the software, not ownership of its code or assets.
- The plugin may be used to produce original music, including commercial work.
- Redistribution, unlawful reverse engineering and resale of the software are prohibited.
- Mandatory consumer rights remain applicable.

RENDERED AUDIO

- Rendered kicks may be used within original personal or commercial productions.
- The factory presets, embedded IRs and other assets remain property of 909VOLTS.
- Do not redistribute isolated factory content or extracted embedded assets.
- See the supplied EULA for the complete licence terms.

BEFORE COMMERCIAL RELEASE

CHECKLIST 909VOLTS

- Replace company name, address, email, governing law and date in every [PLACEHOLDER] field.
- Have the EULA, privacy terms, refunds, VAT and store terms reviewed by a professional.
- Digitally sign the installer and binaries, retain versions and checksums, and test a clean installation.
- The included legal documents are working drafts, not legal advice.

BUILD 0.7.0 / MANUAL GENERATED FROM THE VERIFIED PLUGIN UI / © 2026 909VOLTS