

```

{
  "python format string": "{:03x} {:0{datasize}x}",
  "can_id":
  {
    "26": {
      "source"      : "chasis",
      "execution"   : "power train",
      "name"        : "break operation indicator",
      "level"       : "command",
      "type"        : "operation",
      "period"      : 10,
      "datasize"    : 2,
      "min"         : 0,
      "max"         : 1023,
      "carlaVar"    : "brake"
    },
    "36": {
      "source"      : "power train",
      "execution"   : "chasis",
      "name"        : "break output indicator",
      "level"       : "report",
      "type"        : "output",
      "period"      : 10,
      "datasize"    : 2,
      "min"         : 0,
      "max"         : 1023,
      "carlaVar"    : "brake"
    },
    "326": {
      "source"      : "power train",
      "execution"   : "chasis",
      "name"        : "break oil indicator",
      "level"       : "report",
      "type"        : "dummy",
      "period"      : 50,
      "datasize"    : 2,
      "min"         : 0,
      "max"         : 1023,
      "carlaVar"    : null
    },
    "346": {
      "source"      : "power train",
      "execution"   : "chasis",
      "name"        : "anti-lcok brake operation",
      "level"       : "report",
      "type"        : "dummy",
      "period"      : 50,
      "datasize"    : 1,
      "min"         : 0,
      "max"         : 1,
      "carlaVar"    : null
    },
    "47": {
      "source"      : "chasis",
      "execution"   : "power train",
      "name"        : "accelerator pedal operation indicator",
      "level"       : "command",
      "type"        : "dummy",
      "period"      : 10,
      "datasize"    : 2,
      "min"         : 0,
      "max"         : 1023,
      "carlaVar"    : "throttle"
    },
  },

```

```

"57": {
  "source"      : "power train",
  "execution"   : "chassis",
  "name"        : "throttle position",
  "level"       : "report",
  "type"        : "output",
  "period"      : 10,
  "datasize"    : 2,
  "min"         : 0,
  "max"         : 1023,
  "carlaVar"    : "throttle"
},
"367": {
  "source"      : "power train",
  "execution"   : "chassis",
  "name"        : "throttle adjustment",
  "level"       : "report",
  "type"        : "output",
  "period"      : 50,
  "datasize"    : 2,
  "min"         : 0,
  "max"         : 1023,
  "carlaVar"    : "kmh"
},
"67": {
  "source"      : "power train",
  "execution"   : "chassis",
  "name"        : "engine rpm",
  "level"       : "report",
  "type"        : "measurement",
  "period"      : 10,
  "datasize"    : 4,
  "min"         : [0, -32767],
  "max"         : [65535, 32767],
  "carlaVar"    : "rpm"
},
"387": {
  "source"      : "power train",
  "execution"   : "chassis",
  "name"        : "engine cooling water temperature",
  "level"       : "report",
  "type"        : "dummy",
  "period"      : 50,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : 255,
  "carlaVar"    : null
},
"397": {
  "source"      : "power train",
  "execution"   : "chassis",
  "name"        : "engine malfunction",
  "level"       : "alert",
  "type"        : "dummy",
  "period"      : 50,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : 255,
  "carlaVar"    : null
},
"88": {
  "source"      : "chassis",
  "execution"   : "power train",
  "name"        : "steering wheel operation position",

```

```

        "level"      : "command",
        "type"       : "operation",
        "period"     : 10,
        "datasize"   : 2,
        "min"        : -511,
        "max"        : 511,
        "carlaVar"   : "steer"
    },
    "98": {
        "source"      : "power train",
        "execution"    : "chassis",
        "name"         : "power steering wheel output indicator",
        "level"        : "report",
        "type"         : "output",
        "period"       : 10,
        "datasize"     : 2,
        "min"          : 0,
        "max"          : 100,
        "carlaVar"     : "steer"
    },
    "408": {
        "source"      : "power train",
        "execution"    : "chassis",
        "name"         : "tire angle",
        "level"        : "report",
        "type"         : "output",
        "period"       : 10,
        "datasize"     : 2,
        "min"          : 0,
        "max"          : 1,
        "carlaVar"     : "tire_angle"
    },
    "109": {
        "source"      : "chassis",
        "execution"    : "power train",
        "name"         : "shift position switch",
        "level"        : "command",
        "type"         : "operation",
        "period"       : 10,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : [10, 20],
        "carlaVar"     : "gear"
    },
    "119": {
        "source"      : "power train",
        "execution"    : "chassis",
        "name"         : "shift position",
        "level"        : "report",
        "type"         : "output",
        "period"       : 10,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : [1, 2, 4, 8, 10],
        "carlaVar"     : "gear"
    },
    "440": {
        "source"      : "chassis",
        "execution"    : "power train",
        "name"         : "engine start button",
        "level"        : "command",
        "type"         : "operation",
        "period"       : 50,
        "datasize"     : 1,

```

```

        "min"          :0,
        "max"          :1,
        "carlaVar"     : "ignition"
    },
    "410": {
        "source"       : "power train",
        "execution"    : "chassis",
        "name"         : "engine status",
        "level"        : "report",
        "type"         : "output",
        "period"       : 50,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : 1,
        "carlaVar"     : "engine"
    },
    "980": {
        "source"       : "power train",
        "execution"    : "chassis",
        "name"         : "fuel ammount",
        "level"        : "warning",
        "type"         : "dummy",
        "period"       : 500,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : 40,
        "carlaVar"     : null
    },
    "990": {
        "source"       : "power train",
        "execution"    : "chassis",
        "name"         : "battery warning",
        "level"        : "warning",
        "type"         : "dummy",
        "period"       : 500,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : 1,
        "carlaVar"     : null
    },
    "131": {
        "source"       : "chassis",
        "execution"    : "body",
        "name"         : "right/left turn signal, hazzard switch",
        "level"        : "command",
        "type"         : "operation",
        "period"       : 10,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : [1,2,4],
        "carlaVar"     : "lightTurn"
    },
    "141": {
        "source"       : "body",
        "execution"    : "chassis",
        "name"         : "turn signal indicator",
        "level"        : "report",
        "type"         : "output",
        "period"       : 10,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : [1,2,3],
        "carlaVar"     : "lightTurn"
    },

```

```

"152": {
  "source"      : "chasis",
  "execution"   : "body",
  "name"        : "horn switch",
  "level"       : "command",
  "type"        : "operation",
  "period"      : 10,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : 1,
  "carlaVar"    : null
},
"162": {
  "source"      : "body",
  "execution"   : "chasis",
  "name"        : "horn operation",
  "level"       : "report",
  "type"        : "output",
  "period"      : 10,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : 1,
  "carlaVar"    : null
},
"423": {
  "source"      : "chasis",
  "execution"   : "body",
  "name"        : "position/head lights/high beam switch",
  "level"       : "command",
  "type"        : "operation",
  "period"      : 50,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : [1,2,4,8],
  "carlaVar"    : "lightFront"
},
"433": {
  "source"      : "chasis",
  "execution"   : "body",
  "name"        : "headligh flashing switch",
  "level"       : "command",
  "type"        : "operation",
  "period"      : 50,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : 8,
  "carlaVar"    : "passing"
},
"443": {
  "source"      : "body",
  "execution"   : "chasis",
  "name"        : "position/head lights/high beam indicator",
  "level"       : "report",
  "type"        : "output",
  "period"      : 50,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : [1,2,4,8],
  "carlaVar"    : "lightFront"
},
"604": {
  "source"      : "chasis",
  "execution"   : "body",
  "name"        : "front wiper/intermittent/low/high/washer switch",

```

```

        "level"      : "command",
        "type"       : "operation",
        "period"     : 100,
        "datasize"   : 1,
        "min"        : 0,
        "max"        : [1, 2, 4, 10],
        "carlaVar"   : null
    },
    "614": {
        "source"      : "body",
        "execution"    : "chassis",
        "name"         : "front wiper/intermittent/low/high/washer status",
        "level"        : "report",
        "type"         : "output",
        "period"       : 100,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : [1, 2, 4, 10],
        "carlaVar"     : null
    },
    "625": {
        "source"      : "chassis",
        "execution"    : "body",
        "name"         : "rear wiper/washer switch",
        "level"        : "command",
        "type"         : "operation",
        "period"       : 100,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : [1, 2, 3],
        "carlaVar"     : null
    },
    "635": {
        "source"      : "body",
        "execution"    : "chassis",
        "name"         : "rear wiper/washer status",
        "level"        : "report",
        "type"         : "output",
        "period"       : 100,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : [1, 2, 3],
        "carlaVar"     : null
    },
    "646": {
        "source"      : "body",
        "execution"    : "chassis",
        "name"         : "doors lock/unlock switch",
        "level"        : "command",
        "type"         : "operation",
        "period"       : 100,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : [1, 2, 3],
        "carlaVar"     : null
    },
    "656": {
        "source"      : "body",
        "execution"    : "chassis",
        "name"         : "doors open/close, locked/unlocked indicator",
        "level"        : "report",
        "type"         : "output",
        "period"       : 100,
        "datasize"     : 2,

```

```

        "min"          :0,
        "max"          :[1,2,3],
        "carlaVar"     :null
    },
    "1056": {
        "source"        : "body",
        "execution"     : "chassis",
        "name"          : "door lock drive unit malfunction",
        "level"         : "warning",
        "type"          : "dummy",
        "period"        : 500,
        "datasize"      : 1,
        "min"           : 0,
        "max"           : [1,2,3],
        "carlaVar"      : null
    },
    "457": {
        "source"        : "chassis",
        "execution"     : "power train",
        "name"          : "parking brake",
        "level"         : "command",
        "type"          : "operation",
        "period"        : 50,
        "datasize"      : 1,
        "min"           : 0,
        "max"           : 1,
        "carlaVar"      : "hand_brake"
    },
    "467": {
        "source"        : "power train",
        "execution"     : "chassis",
        "name"          : "parking break status",
        "level"         : "report",
        "type"          : "output",
        "period"        : 50,
        "datasize"      : 1,
        "min"           : 0,
        "max"           : 1,
        "carlaVar"      : "hand_brake"
    },
    "668": {
        "source"        : "chassis",
        "execution"     : "body",
        "name"          : "right door/window lifting switch",
        "level"         : "command",
        "type"          : "operation",
        "period"        : 100,
        "datasize"      : 1,
        "min"           : 0,
        "max"           : [1,2],
        "carlaVar"      : null
    },
    "678": {
        "source"        : "body",
        "execution"     : "chassis",
        "name"          : "right door/window position, limit switch status",
        "level"         : "report",
        "type"          : "output",
        "period"        : 100,
        "datasize"      : 2,
        "min"           : 0,
        "max"           : [1,2,255],
        "carlaVar"      : null
    },
    },

```

```

"689": {
  "source"      : "chasis",
  "execution"   : "body",
  "name"        : "left door/window lifting switch",
  "level"       : "command",
  "type"        : "operation",
  "period"      : 100,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : [1,2],
  "carlaVar"    : null
},
"699": {
  "source"      : "body",
  "execution"   : "chasis",
  "name"        : "left door/window position, limit switch status",
  "level"       : "report",
  "type"        : "output",
  "period"      : 100,
  "datasize"    : 2,
  "min"         : 0,
  "max"         : [1,2,255],
  "carlaVar"    : null
},
"180": {
  "source"      : "body",
  "execution"   : "chasis",
  "name"        : "airbag activation switch",
  "level"       : "report",
  "type"        : "dummy",
  "period"      : 10,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : 1,
  "carlaVar"    : "collision"
},
"1111": {
  "source"      : "body",
  "execution"   : "chasis",
  "name"        : "seat belt sensor",
  "level"       : "report",
  "type"        : "dummy",
  "period"      : 500,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : 1,
  "carlaVar"    : null
},
"1121": {
  "source"      : "body",
  "execution"   : "chasis",
  "name"        : "seat belt alarm",
  "level"       : "warning",
  "type"        : "dummy",
  "period"      : 500,
  "datasize"    : 1,
  "min"         : 0,
  "max"         : 1,
  "carlaVar"    : null
},
"1132": {
  "source"      : "body",
  "execution"   : "chasis",
  "name"        : "hood open/close switch",

```



```

        "level"      : "report",
        "type"       : "dummy",
        "period"     : 500,
        "datasize"   : 1,
        "min"        : 0,
        "max"        : 1,
        "carlaVar"   : null
    },
    "1143": {
        "source"      : "body",
        "execution"    : "chassis",
        "name"         : "trunk open/close switch",
        "level"        : "report",
        "type"         : "dummy",
        "period"       : 500,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : 1,
        "carlaVar"     : null
    },
    "1154": {
        "source"      : "power train",
        "execution"    : "chassis",
        "name"         : "eco-driving judgement",
        "level"        : "report",
        "type"         : "dummy",
        "period"       : 500,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : 1,
        "carlaVar"     : null
    },
    "2100": {
        "datasize"     : 1,
        "level"        : "command",
        "carlaVar"     : "manual"
    },
    "2110": {
        "datasize"     : 1,
        "level"        : "report",
        "carlaVar"     : "manual"
    },
    "1001": {
        "source"      : "body",
        "execution"    : "chassis",
        "name"         : "closest radar point",
        "level"        : "report",
        "type"         : "output",
        "period"       : 10,
        "datasize"     : 2,
        "min"          : 0,
        "max"          : 10000,
        "carlaVar"     : "radar"
    },
    "1012": {
        "source"      : "body",
        "execution"    : "chassis",
        "name"         : "closest lidar point",
        "level"        : "report",
        "type"         : "output",
        "period"       : 10,
        "datasize"     : 4,
        "min"          : 0,
        "max"          : 32767,

```

```

        "carlaVar"    : "lidar"
    },
    "1313": {
        "source": "body",
        "execution": "infotainment",
        "name": "lane departure sound alert",
        "level": "command",
        "type": "boolean",
        "period": 10,
        "datasize": 1,
        "min": 0,
        "max": 1,
        "carlaVar": "lane_departure_sound"
    },
    "1200": {
        "source"      : "body",
        "execution"    : "chasis",
        "name"         : "collision alert trigger",
        "level"        : "command",
        "type"         : "operation",
        "period"       : 10,
        "datasize"     : 1,
        "min"          : 0,
        "max"          : 1,
        "carlaVar"     : "collision"
    }
}
}
}

```