```
/**
 1
 2
 3
        @copyright © 2010 - 2020, Fraunhofer-Gesellschaft zur Foerderung der
 4
      * angewandten Forschung e.V. All rights reserved.
 5
 6
      * BSD 3-Clause License
 7
      * Redistribution and use in source and binary forms, with or without
 8
      * modification, are permitted provided that the following conditions are met:
 9
      * 1. Redistributions of source code must retain the above copyright notice,
10
            this list of conditions and the following disclaimer.
11
       2. Redistributions in binary form must reproduce the above copyright
12
            notice, this list of conditions and the following disclaimer in the
13
            documentation and/or other materials provided with the distribution.
14
      * 3. Neither the name of the copyright holder nor the names of its
15
            contributors may be used to endorse or promote products derived from
16
            this software without specific prior written permission.
17
18
      * THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS"
19
      * AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
20
      * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
21
      * ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE
22
      * LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR
23
      * CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF
24
      * SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS
25
      * INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN
26
      * CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
27
      * ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE
28
      * POSSIBILITY OF SUCH DAMAGE.
29
30
      * We kindly request you to use one or more of the following phrases to refer
31
      * to foxBMS in your hardware, software, documentation or advertising
32
      * materials:
33
34
      * ″ This product uses parts of foxBMS&req; ″
35
36
      * ″ This product includes parts of foxBMS® ″
37
38
      * ″ This product is derived from foxBMS&req; ″
39
40
      */
41
     /**
42
43
      * @file
                database cfq.c
44
      * @author foxBMS Team
45
      * @date
                18.08.2015 (date of creation)
46
      * @ingroup ENGINE CONF
      * @prefix DATA
47
48
49
      * @brief Database configuration
50
51
      * Configuration of database module
52
```

```
53 */
54
55
     /*======= Includes ======*/
56
     #include "database cfg.h"
57
58
     /*======= Macros and Definitions ===========*/
59
60
     /*======= Static Constant and Variable Definitions ======*/
61
62
     * data block: cell voltage
63
64
     static DATA BLOCK CELLVOLTAGE s data block cellvoltage;
65
66 /**
* data block: cell temperature
68
69
     static DATA_BLOCK_CELLTEMPERATURE_s data_block_celltemperature;
70
71 /**
72
    * data block: sox
73 */
74 static DATA_BLOCK_SOX_s data_block_sox;
75
76 /**
77 * data block: sof
78 */
79    static DATA_BLOCK_SOF_s data_block_sof;
80
81 /**
* data block: balancing control
83
84
     static DATA_BLOCK_BALANCING_CONTROL_s data_block_control_balancing;
85
86 /**
* data block: balancing feedback
88
89
    static DATA_BLOCK_BALANCING_FEEDBACK_s data_block_feedback_balancing;
90
91 /**
92
     * data block: current measurement
93
     * /
94
     static DATA_BLOCK_CURRENT_SENSOR_s data_block_curr_sensor;
95
96 /**
97 * data block: ADC
98
99
     static DATA BLOCK HW INFO s data block hwinfo;
100
101
     /**
102
     * data block: can state request
103
     * /
104
     static DATA_BLOCK_STATEREQUEST_s data_block_staterequest;
```

```
105
106
     /**
107
     * data block: LTC minimum and maximum values
108
      * /
109
     static DATA BLOCK MINMAX s data block minmax;
110
111
     /**
112
     * data block: isometer measurement
113
114
     static DATA_BLOCK_ISOMETER_s data_block_isometer;
115
     /**
116
117
      * data block: error flags
118
119
     static DATA BLOCK ERRORSTATE s data block errors;
120
121
122
      * data block: maximum safety limit violations
123
124
     static DATA BLOCK MSL FLAG s data block MSL;
125
     /**
126
127
      * data block: recommended safety limit violations
128
129
     static DATA_BLOCK_RSL_FLAG_s data_block_RSL;
130
      /**
131
132
      * data block: maximum operating limit violations
133
      * /
134
     static DATA BLOCK MOL FLAG s data block MOL;
135
     /**
136
137
     * data block: moving mean current and power
138
139
      static DATA_BLOCK_MOVING_AVERAGE_s data_block_mov_average;
140
141
     /**
142
      * data block: contactor feedback
143
144
     static DATA BLOCK CONTFEEDBACK s data block contfeedback;
145
     /**
146
147
      * data block: interlock feedback
148
149
     static DATA BLOCK ILCKFEEDBACK s data block ilckfeedback;
150
      /**
151
152
     * data block: slave control
153
154
     static DATA_BLOCK_SLAVE_CONTROL_s data_block_slave_control;
155
     /**
156
```

```
157
       * data block: system state
158
159
      static DATA BLOCK SYSTEMSTATE s data block systemstate;
160
      /**
161
162
      * data block: open wire check
163
       * /
164
      static DATA BLOCK OPENWIRE s data block open wire;
165
      /**
166
167
      * data block: LTC diagnosis values
168
169
      static DATA BLOCK LTC DEVICE PARAMETER s data block ltc diagnosis;
170
      /**
171
172
      * data block: LTC ADC accuracy verification
173
174
      static DATA_BLOCK_LTC_ADC_ACCURACY_s data_block_ltc_adc_accuracy;
175
176
177
      * data block: LTC ADC accuracy verification
178
179
      static DATA BLOCK ALLGPIOVOLTAGE s data block ltc allgpiovoltages;
180
      /**
181
182
      * data block: SOH of contactors
183
184
      static DATA_BLOCK_CONT_SOH_s data_block_contactor_soh;
185
      /**
186
187
      * @brief channel configuration of database (data blocks)
188
189
       * all data block managed by database are listed here (address, size, consistency type)
190
191
       * /
192
      static DATA_BASE_HEADER_s data_base_header[] = {
                                                               data base header[] defines the pair of (dataPointer, size). With
193
                                                               this info, we can access all the contents in the database.
194
               (void*) (&data block cellvoltage),
195
              sizeof(DATA_BLOCK_CELLVOLTAGE_s)
196
          },
197
          {
198
               (void*) (&data_block_celltemperature),
              sizeof(DATA BLOCK CELLTEMPERATURE s)
199
200
          },
201
202
               (void*) (&data_block_sox),
203
              sizeof(DATA BLOCK SOX s)
204
          },
205
206
               (void*) (&data_block_control_balancing),
              sizeof(DATA BLOCK BALANCING CONTROL s)
207
208
          },
```

```
209
          {
210
               (void*) (&data block feedback balancing),
211
              sizeof(DATA_BLOCK_BALANCING_FEEDBACK_s)
212
          },
213
214
               (void*) (&data_block_curr_sensor),
215
               sizeof(DATA BLOCK CURRENT SENSOR s)
216
          },
217
218
               (void*) (&data_block_hwinfo),
              sizeof(DATA_BLOCK_HW_INFO_s)
219
220
          },
221
222
               (void*) (&data_block_staterequest),
223
               sizeof(DATA_BLOCK_STATEREQUEST_s)
224
          },
225
226
               (void*) (&data_block_minmax),
227
              sizeof(DATA_BLOCK_MINMAX_s)
228
          },
229
230
               (void*) (&data_block_isometer),
231
               sizeof(DATA BLOCK ISOMETER s)
232
          },
233
          {
234
               (void*) (&data_block_slave_control),
235
               sizeof(DATA_BLOCK_SLAVE_CONTROL_s)
236
          },
237
238
               (void*) (&data_block_open_wire),
239
              sizeof(DATA_BLOCK_OPENWIRE_s)
240
          },
241
242
               (void*) (&data_block_ltc_diagnosis),
243
              sizeof(DATA_BLOCK_LTC_DEVICE_PARAMETER_s)
244
          },
245
246
               (void*) (&data block ltc adc accuracy),
247
               sizeof(DATA_BLOCK_LTC_ADC_ACCURACY_s)
248
          },
249
          {
250
               (void*) (&data_block_errors),
251
               sizeof(DATA_BLOCK_ERRORSTATE_s)
252
          },
253
254
               (void*) (&data_block_MSL),
255
               sizeof(DATA BLOCK MSL FLAG s)
256
          },
257
258
               (void*) (&data_block_RSL),
259
               sizeof(DATA_BLOCK_RSL_FLAG_s)
260
          },
```

```
261
          {
262
               (void*) (&data block MOL),
263
              sizeof(DATA_BLOCK_MOL_FLAG_s)
264
          },
265
266
               (void*) (&data_block_mov_average),
267
              sizeof(DATA BLOCK MOVING AVERAGE s)
268
          },
269
270
               (void*) (&data_block_contfeedback),
271
              sizeof(DATA_BLOCK_CONTFEEDBACK_s)
272
          },
273
274
               (void*) (&data_block_ilckfeedback),
275
              sizeof(DATA BLOCK ILCKFEEDBACK s)
276
          },
277
278
               (void*) (&data_block_systemstate),
279
              sizeof(DATA BLOCK SYSTEMSTATE s)
280
          },
281
282
               (void*) (&data_block_sof),
283
              sizeof(DATA BLOCK SOF s)
284
          },
285
          -{
286
               (void*) (&data block ltc allgpiovoltages),
287
              sizeof(DATA BLOCK ALLGPIOVOLTAGE s)
288
          },
289
290
               (void*) (&data block contactor soh),
291
              sizeof(DATA BLOCK CONT SOH s)
292
          },
293
      };
294
295
296
      /*====== Extern Constant and Variable Definitions =======*/
297
      /**
298
299
       * @brief device configuration of database
300
301
       * all attributes of device configuration are listed here (pointer to channel list, number of channels)
302
      const DATA_BASE_HEADER_DEV_s data_base_dev = {
303
304
           .nr of blockheader = sizeof(data base header)/sizeof(DATA BASE HEADER s),
                                                                                          /* number of blocks (and block
          headers) */
                                                            data base dev contains two values:
305
          .blockheaderptr
                               = &data_base_header[0],
                                                              * Total number of data pairs in data_base_header
306
      };
                                                              * The pointer to data base header.
307
      /*========= Static Function Prototypes ====<del>with data base dev, we can access</del> the database anywhere. Hence, this
308
309
                                                            variable exposed in the header file.
310
      /*========= Static Function Implementations ===========*/
311
```

312 /*======= Extern Function Implementations =======*/
313