

ROUTAGE EIGRP

!!Sur R1

Enable

Conf t

Router eigrp 92

No auto-summary

Network 200.158.1.0

Network 100.15.1.28 0.0.0.3

!!Sur R2

Enable

Conf t

Router eigrp 92

No auto-summary

Network 179.58.0.0

Network 100.15.1.28 0.0.0.3

!!Sur R3

Enable

Conf t

Router eigrp 92

No auto-summary

Network 179.58.0.0

Network 64.0.0.0 0.0.0.3

Network 25.0.0.0 0.0.0.3

!!Sur R4

Enable

Conf t

Router eigrp 92

No auto-summary

Network 64.0.0.0 0.0.0.3

Network 193.15.15.0

!!Sur R5

Enable

Conf t

Router eigrp 92

No auto-summary

Network 193.15.15.0

Network 100.55.0.0 0.0.0.3

!!Sur R6

Enable

Conf t

Router eigrp 92

No auto-summary

Network 100.55.0.0 0.0.0.3

Network 200.18.100.0

Network 200.18.99.0

Network 8.0.0.0

!!Sur R7

Enable

Conf t

Router eigrp 92

No auto-summary

Network 25.0.0.0 0.0.0.3

Network 200.18.100.0

+++++

Sur Routeur 192.168.1.254/10.10.10.5

Enable

Conf t

Interface fa0/0

Ip address 192.168.1.254 255.255.255.0

No shutdown

Interface se0/0/0

Ip address 10.10.10.5 255.255.255.252

No shutdown

Clock rate 4000000

Sur Routeur 192.168.2.254/10.10.10.6

Enable

Conf t

Interface fa0/0

Ip address 192.168.2.254 255.255.255.0

No shutdown

Interface se0/0/0

Ip address 10.10.10.6 255.255.255.252

No shutdown

ON AJOUTE LE ROUTAGE STATIQUE

!!!Sur Routeur 192.168.1.254/10.10.10.5

enable

conf t

ip route 192.168.2.0 255.255.255.0 10.10.10.6

!!!Sur Routeur 192.168.2.254/10.10.10.6

enable

```
conf t
```

```
ip route 192.168.1.0 255.255.255.0 10.10.10.5
```