

Le routage

Adresse IP

Masque de sous-reseau

Passerelle par défaut

Routage Static - CISCO

Syntaxe

Ip route DESTINATION MASK PASSERELLE

Sur R1

Enable

Conf t

```
Ip route 0.0.0.0 0.0.0.0 100.15.1.30
```

Sur R2

Enable

Conf t

```
Ip route 0.0.0.0 0.0.0.0 179.58.0.2
```

```
Ip route 200.158.1.0 255.255.255.0 100.15.1.29
```

Sur R3

Enable

Conf t

```
Ip route 0.0.0.0 0.0.0.0 25.0.0.2
```

```
Ip route 200.158.1.0 255.255.255.0 179.58.0.1
```

```
Ip route 193.15.15.0 255.255.255.0 64.0.0.2
```

Sur R4

Enable

Conf t

```
Ip route 0.0.0.0 0.0.0.0 193.15.15.2
```

```
Ip route 200.158.1.0 255.255.255.0 64.0.0.1
```

```
Ip route 179.58.0.0 255.255.0.0 64.0.0.1
```

Sur R5

```
Enable
```

```
Conf t
```

```
Ip route 0.0.0.0 0.0.0.0 100.55.0.1
```

```
Ip route 200.158.1.0 255.255.255.0 193.15.15.1
```

```
Ip route 179.58.0.0 255.255.0.0 193.15.15.1
```

Sur R6

```
Enable
```

```
Conf t
```

```
Ip route 200.158.1.0 255.255.255.0 200.18.99.2
```

```
Ip route 179.58.0.0 255.255.0.0 200.18.99.2
```

```
Ip route 193.15.15.0 255.255.255.0 100.55.0.2
```

Sur R7

```
Enable
```

```
Conf t
```

```
Ip route 0.0.0.0 0.0.0.0 200.18.99.1
```

```
Ip route 200.158.1.0 255.255.255.0 25.0.0.1
```

```
Ip route 179.58.0.0 255.255.0.0 25.0.0.1
```

```
Ip route 193.15.15.0 255.255.255.0 25.0.0.1
```