

What is the command to begin the configuration of an extended access list with the name **ACL**?

Ans:

RT1(config)# ip access-list extended ACL

Cisco Packet Tracer - /Users/abdiabera/Desktop/ALLpacketTracer/4.5.13-packet-tracer-configure-extended-acls-scenario-2.pka - Guest - 2026-05-03 05:04:22

Logical Physical x: 214, y: 346

Addressing Table

	Device	IP Address	Subnet Mask
PC1	NIC	172.31.1.101	255.255.0.0
PC2	NIC	172.31.1.102	255.255.0.0
PC3	NIC	172.31.1.103	255.255.0.0
Server1	NIC	64.101.255.254	blank
Server2	NIC	64.103.255.254	blank

Instructions

Server1.

```
RT1 (config-ext-nacl) # deny icmp host 172.31.1.103 host 64.101.255.254
```

b. Enter the statement that denies ICMP access from PC3 to Server2.

```
RT1 (config-ext-nacl) # deny icmp host 172.31.1.103 host 64.103.255.254
```

Step 4: Permit all other IP traffic

Time Elapsed: 00:13:00 Completion: 100%

Time: 00:12:37

Scenario 0

New Delete Toggle PDU List Window

Objectives

Part 1: Configure a Named Extended ACL

Part 2: Apply and Verify the Extended ACL

Background / Scenario

In this scenario, specific devices on the LAN are allowed to various services on servers located on the internet.

Instructions

Part 1: Configure a Named Extended ACL

Configure one named ACL to implement the following policy:

Block HTTP and HTTPS access from PC1 to Server1 and

Time Elapsed: 00:06:31 Completion: 100%

Time: 00:06:19

RT1

```
RT1 (config-if) # ip access-group ACL in
RT1 (config-if) # copy running-config startup-config
% Invalid input detected at "" marker.
RT1 (config-if) # end
RT1 #
RT1 (config) # copy running-config startup-config
Destination filename [startup-config]:
Building configuration...
[OK]
RT1 #
RT1 # enable
RT1 # configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
RT1 (config) # ip access-list extended ACL
RT1 (config-ext-nacl) # deny tcp host 172.31.1.101 host 64.101.255.254 eq 80
RT1 (config-ext-nacl) # deny tcp host 172.31.1.101 host 64.101.255.254 eq 443
RT1 (config-ext-nacl) # deny tcp host 172.31.1.101 host 64.103.255.254 eq 80
RT1 (config-ext-nacl) # deny tcp host 172.31.1.101 host 64.103.255.254 eq 443
RT1 (config-ext-nacl) # deny tcp host 172.31.1.102 host 64.101.255.254 eq 21
RT1 (config-ext-nacl) # deny tcp host 172.31.1.102 host 64.103.255.254 eq 21
RT1 (config-ext-nacl) # deny icmp host 172.31.1.103 host 64.101.255.254
RT1 (config-ext-nacl) # deny icmp host 172.31.1.103 host 64.103.255.254
RT1 (config-ext-nacl) # permit ip any any
RT1 (config-ext-nacl) # exit
```

On which interface should the named ACL be applied, and in which direction?

Enter the configuration commands to apply the ACL to the interface.

Ans:

ACL must be applied to Gig0/1 inbound direction