

Lab Report

Lab Report

Time Spent: 09:16

Score: 5/5 (100%)

Pass

Passing Score: 5/5 (100%)

TASK SUMMARY

Required Actions & Questions

Q1 What is the maximum number of logs that can be displayed?

Your answer: 50

Correct answer: 50

General settingsHide Details

Change the number of logs shown in the GUI to 25

Set the log file size to 250000 bytes

Enable remote logging

Configure remote loggingHide Details

Source Address set to Any

IP Protocol set to IPv4

Remote log server set to 192.168.0.10

Remote Syslog Contents:

- System Events
- Firewall Events

Q2 What is the maximum number of logs that can be displayed after configuring the system log settings?

Your answer: 25

Correct answer: 25

EXPLANATION

Complete this lab as follows:

1. Sign in to the pfSense Management console.
 - a. In the Username field, enter **admin**.
 - b. In the Password field, enter **P@ssw0rd** (zero).
 - c. Select **SIGN IN** or press **Enter**.
2. Access the system log settings.
 - a. From the pfSense menu bar, select **Status > System Logs**.
 - b. In the top right, select **Answer Questions**.
 - c. Answer Question 1.
3. Configure the general logging options.
 - a. Under the *Status* breadcrumb, select **Settings**.
 - b. Set the GUI Log Entries field to **25** to show only 25 logs at a time in the GUI.
 - c. Set the Log file size field to **250000** bytes (250 KB) to set the maximum size of each log file.
4. Configure remote logging.
 - a. Scroll to the bottom and, under Remote Logging Options, select **Enable Remote Logging**.
 - b. Make sure the options are set as follows:
 - Source address: **Default (any)**
 - IP protocol: **IPv4**
 - Remote log servers: **192.168.0.10**
 - c. For Remote Syslog Contents, select the following:
 - **System Events**

- **Firewall Events**

- d. Select **Save**.
5. View the results of the changes made to the number of logs shown.
 - a. Under the *Status* breadcrumb, select **System**.
 - b. Answer Question 2.
 - c. Select **Score Lab**.