PC2

Physical | Config | Desktop | Programming | Attributes

IP Configuration X

Interface: FastEthernet0

IP Configuration

- DHCP
- Static

IPv4 Address	192.168.2.2
Subnet Mask	255.255.255.0
Default Gateway	192.168.2.1
DNS Server	0.0.0.0

IPv6 Configuration

- Automatic
- Static

IPv6 Address	/
Link Local Address	FE80::201:96FF:FE43:65D5
Default Gateway	
DNS Server	

802.1X

- [ ] Use 802.1X Security

Authentication	MD5
Username	
Password	

PC4

Physical | Config | Desktop | Programming | Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

- DHCP
- Static

IPv4 Address: 192.168.3.2

Subnet Mask: 255.255.255.0

Default Gateway: 192.168.3.1

DNS Server: 0.0.0.0

IPv6 Configuration

- Automatic
- Static

IPv6 Address: /

Link Local Address: FE80::230:F2FF:FE6D:19E9

Default Gateway:

DNS Server:

802.1X

- [ ] Use 802.1X Security

Authentication: MD5

Username:

Password:

PC6

Physical | Config | Desktop | Programming | Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

- DHCP
- Static

IPv4 Address: 192.168.4.2

Subnet Mask: 255.255.255.0

Default Gateway: 192.168.4.1

DNS Server: 0.0.0.0

IPv6 Configuration

- Automatic
- Static

IPv6 Address: /

Link Local Address: FE80::201:C9FF:FE72:1DD6

Default Gateway:

DNS Server:

802.1X

- [ ] Use 802.1X Security

Authentication: MD5

Username:

Password:

PC13

Physical | Config | Desktop | Programming | Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

- DHCP
- Static

IPv4 Address: 192.168.5.3

Subnet Mask: 255.255.255.0

Default Gateway: 192.168.5.1

DNS Server: 0.0.0.0

IPv6 Configuration

- Automatic
- Static

IPv6 Address: /

Link Local Address: FE80::201:42FF:FE0A:1353

Default Gateway:

DNS Server:

802.1X

- [ ] Use 802.1X Security

Authentication: MD5

Username:

Password:

PC10

Physical | Config | Desktop | Programming | Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

- DHCP
- Static

IPv4 Address	192.168.6.2
Subnet Mask	255.255.255.0
Default Gateway	192.168.6.1
DNS Server	0.0.0.0

IPv6 Configuration

- Automatic
- Static

IPv6 Address	/
Link Local Address	FE80::201:63FF:FE64:2476
Default Gateway	
DNS Server	

802.1X

- [ ] Use 802.1X Security

Authentication	MD5
Username	
Password	

PC8

Physical | Config | Desktop | Programming | Attributes

IP Configuration X

Interface: FastEthernet0

IP Configuration

- DHCP
- Static

IPv4 Address	192.168.7.2
Subnet Mask	255.255.255.0
Default Gateway	192.168.7.1
DNS Server	0.0.0.0

IPv6 Configuration

- Automatic
- Static

IPv6 Address	/
Link Local Address	FE80::240:BFF:FEE4:C305
Default Gateway	
DNS Server	

802.1X

- [ ] Use 802.1X Security

Authentication	MD5
Username	
Password	

PC0

Physical | Config | Desktop | Programming | Attributes

IP Configuration

X

Interface: FastEthernet0

IP Configuration

- DHCP
- Static

IPv4 Address	192.168.1.2
Subnet Mask	255.255.255.0
Default Gateway	192.168.1.1
DNS Server	0.0.0.0

IPv6 Configuration

- Automatic
- Static

IPv6 Address	/
Link Local Address	FE80::203:E4FF:FE7B:26AA
Default Gateway	
DNS Server	

802.1X

- [ ] Use 802.1X Security

Authentication	MD5
Username	
Password	

Router7

Physical Config CLI Attributes

IOS Command Line Interface

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up
ip address 16.0.0.2 255.0.0.0
Router(config-if)#ip address 16.0.0.2 255.0.0.0
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#
Router(config-if)#enable
                    ^
% Invalid input detected at '^' marker.

Router(config-if)#conf t
%Invalid hex value
Router(config)#router ospf 1
Router(config-router)#network 192.168.1.0 0.0.0.255 area 0
Router(config-router)#network 10.0.0.0 0.0.0.3 area 0
Router(config-router)#network 16.0.0.0 0.0.0.3 area 0
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

00:19:43: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.2.1 on Serial0/0 from LOADING to FULL, Loading
Done

00:21:33: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.7.1 on Serial0/1 from LOADING to FULL, Loading
Done
```

Copy Paste

Router8

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface Serial0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up
ip address 15.0.0.2 255.0.0.0
Router(config-if)#ip address 15.0.0.2 255.0.0.0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#no shutdown
Router(config-if)#clock rate 64000
Router(config-if)#ip address 16.0.0.1 255.0.0.0
Router(config-if)#ip address 16.0.0.1 255.0.0.0
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#router ospf 1
Router(config-router)#network 192.168.7.0 0.0.0.255 area 0
Router(config-router)#network 15.0.0.0 0.0.0.3 area 0
Router(config-router)#network 16.0.0.0 0.0.0.3 area 0
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

00:20:38: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.6.1 on Serial0/0 from LOADING to FULL, Loading
Done

00:20:39: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.1.1 on Serial0/1 from LOADING to FULL, Loading
Done
```

Copy Paste

Router9

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface Serial0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0, changed state to up
ip address 14.0.0.2 255.0.0.0
Router(config-if)#ip address 14.0.0.2 255.0.0.0
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown
Router(config-if)#ip address 15.0.0.1 255.0.0.0
Router(config-if)#ip address 15.0.0.1 255.0.0.0
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#router ospf 1
Router(config-router)#network 192.168.6.0 0.0.0.255 area 0
Router(config-router)#network 14.0.0.0 0.0.0.3 area 0
Router(config-router)#network 15.0.0.0 0.0.0.3 area 0
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

00:20:02: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.5.1 on Serial0/0 from LOADING to FULL, Loading
Done

00:20:46: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.7.1 on Serial0/1 from LOADING to FULL, Loading
Done
```

Copy Paste

Router10

Physical Config CLI Attributes

IOS Command Line Interface

```
Router(config-if)#no ip address
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#clock rate 64000
This command applies only to DCE interfaces
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#no ip address
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#ip address 11.0.0.1 255.0.0.0
Router(config-if)#ip address 11.0.0.1 255.0.0.0
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#
Router(config-if)#router ospf 1
Router(config-router)#network 192.168.2.0 0.0.0.255 area 0
Router(config-router)#network 10.0.0.0 0.0.0.3 area 0
Router(config-router)#network 11.0.0.0 0.0.0.3 area 0
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

00:19:32: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.1.1 on Serial0/0 from LOADING to FULL, Loading
Done

00:19:55: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.3.1 on Serial0/1 from LOADING to FULL, Loading
Done
```

Copy Paste

Router11

Physical Config CLI Attributes

IOS Command Line Interface

```
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface Serial0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0, changed state to up
ip address 11.0.0.2 255.0.0.0
Router(config-if)#ip address 11.0.0.2 255.0.0.0
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown
Router(config-if)#ip address 12.0.0.1 255.0.0.0
Router(config-if)#ip address 12.0.0.1 255.0.0.0
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#
Router(config-if)#router ospf 1
Router(config-router)#network 192.168.3.0 0.0.0.255 area 0
Router(config-router)#network 11.0.0.0 0.0.0.3 area 0
Router(config-router)#network 12.0.0.0 0.0.0.3 area 0
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

00:19:45: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.2.1 on Serial0/0 from LOADING to FULL, Loading
Done

00:20:04: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.4.1 on Serial0/1 from LOADING to FULL, Loading
Done
```

Copy Paste

Router12

Physical Config CLI Attributes

IOS Command Line Interface

```
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface Serial0/0
Router(config-if)#ip address 12.0.0.2 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown
Router(config-if)#ip address 13.0.0.1 255.0.0.0
Router(config-if)#ip address 13.0.0.1 255.0.0.0
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#router ospf 1
Router(config-router)#network 192.168.4.0 0.0.0.255 area 0
Router(config-router)#network 12.0.0.0 0.0.0.3 area 0
Router(config-router)#network 13.0.0.0 0.0.0.3 area 0
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

00:19:55: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.3.1 on Serial0/0 from LOADING to FULL, Loading
Done

00:20:09: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.5.1 on Serial0/1 from LOADING to FULL, Loading
Done
```

Copy Paste

Router13

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface Serial0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up
ip address 13.0.0.2 255.0.0.0
Router(config-if)#ip address 13.0.0.2 255.0.0.0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#no shutdown
Router(config-if)#clock rate 64000
Router(config-if)#ip address 14.0.0.1 255.0.0.0
Router(config-if)#ip address 14.0.0.1 255.0.0.0
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#router ospf 1
Router(config-router)#network 192.168.5.0 0.0.0.255 area 0
Router(config-router)#network 13.0.0.0 0.0.0.3 area 0
Router(config-router)#network 14.0.0.0 0.0.0.3 area 0
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

00:20:00: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.4.1 on Serial0/0 from LOADING to FULL, Loading
Done

00:20:10: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.6.1 on Serial0/1 from LOADING to FULL, Loading
Done
```

Copy Paste