

1 SMA Login

Overview

You must log in to SMA in order to use applications in SMA. There are two login methods: a user login and a person login. Each application requires a specific login.

User login

For the user login, three tabs are provided: *HYDRA user*, *Language* and *Settings*.

- *HYDRA user*: This tab represents the actual login. Enter a valid HYDRA user with the relevant password. Use the link *Change password* to change the current password for the active user. First enter the current password, then the new password.
- *Language*: You can select between the languages German, English and Chinese. The selected language is only used once the user has logged in. Before login, the language specified in the browser is used, if possible. If the selected language is not licensed, the system issues an error message informing that SMA is not available in the language selected. A login is then not possible.
- *Settings*: Select the HYDRA system where the user wants to log in.

If you click the button OK, the login with the relevant settings is performed.

Person login

For the person login, three tabs are provided: *Person*, *Language* and *Settings*.

- *Person*: This tab represents the actual login. To identify the person, enter the personnel number in field *Person* or the staff badge number in field *Badge* plus the relevant pincode of the person. Use the link *Change pincode* to change the current pincode for the active person. First enter the current pincode, then the new pincode.



If devices of "dormakaba" are used and you require the pincode for the access control, this pincode must have four digits.

- *Language*: You can select between the languages German, English and Chinese. The selected language is only used once the person has logged in. Before login, the language specified in the browser is used, if possible. If the selected language is not licensed, the system issues an error message informing that SMA is not available in the language selected. A login is then not possible.

- *Settings:* Select the HYDRA system where the person wants to log in. The following settings are available:
 - *Terminal mode:* If the terminal mode is activated, the personal information stored for the session is deleted when you call the application *Time and Attendance*. (Use this mode if the browser is used by several persons for clocking purposes. Here, the person must exit the application *Time and Attendance* on the host when the clocking is performed. This way, other users can perform clockings and the personal data is deleted.)
 - *Show "person" field:* If the terminal mode is activated, this setting or the field *Show "badge" field* must also be activated. If the terminal mode is not activated, you can use this setting to check the relevant person again (i.e. before clocking).
 - *Show "badge" field:* If the terminal mode is activated, this setting or the field *Show "person" field* must also be activated. If the terminal mode is not activated, you can use this setting to check the relevant person again (i.e. before clocking).
 - *Terminal:* Specifies the PZE terminal configured in HYDRA. This configuration is required to collect times. By default, a configuration for the terminal 254 is searched for in HYDRA.
 - *Cost center posting:* If this setting is activated, you can select a cost center when you make a clocking.
 - *Company for cost center posting:* The entry is used as a filter to select a cost center. Only use this field if the cost center posting is activated.
 - *Company for absence reason list:* If a list of absence reasons is stored in the configured terminal, this setting is used to add the absence reasons to the list, which are assigned to this company. (Absence reasons without assignment to a company + absence reasons assigned to this company).

If you click the button OK, the login with the relevant settings is performed.