


1 AIP - on-screen keyboard decimal symbol configuration

Overview

Menu	All AIP input screens
Transaction code	n/a
Function authorization	n/a

You cannot use the numeric on-screen keyboard (virtual keyboard) to enter decimals, if you configure different decimal symbols in the keyboard settings and the regional settings of the operating system.




The screenshot shows the AIP application interface. At the top, there's a title bar with the AIP logo and the text 'Change target cycle for operation 01010100000200010 0010 Turning'. Below this, there's a section for 'Operation 010100000200010 0010 Turning' with fields for Order (010101000002), Article (0101H34729-0010), Handle, Target qty. (50 PCE), Yield (70 PCE), Scrap (0 PCE), and Completion (140%). Below this is a section for 'Workplace 01011004 Turning' with fields for Current status (PRODUCTION), Part (2), Current target cycle (5,000 [Sec./cycle]), and Act. cycle (0,000 [Sec./cycle]). At the bottom, there's a numeric keypad with a red box highlighting the decimal separator field, which currently shows a comma (','). The keypad also has a 'New target cycle' field with a red box highlighting the '5,000' value. The bottom of the screen shows a 'Cancel' button, a 'Change targ. cycle' button, and a timestamp '18-03-16 10:45:09'.


Solution: Keyboard settings and regional settings should match. Example: if you configure a comma "," as the decimal symbol in the regional settings, you also have to select a comma as the decimal separator in the keyboard settings.

Purpose

Every time you start the AIP, the application identifies which decimal symbol is displayed and expected in the input field. The AIP application gets this information from the Windows system setting "region".



Every time you start the on-screen keyboard, the keyboard identifies which decimal symbol is displayed on the numeric keypad. The on-screen keyboard gets this information from the currently selected keyboard settings:



Integration

If you set both configurations correctly (see above), you can use the numeric on-screen keyboard to enter decimals (see the following screenshot):

If the configurations do not match, for example:

- you select the "comma" in the "region" tab of the Windows system settings and
 - you select the "decimal point" in the keyboard settings
- you cannot use the on-screen keyboard to enter the decimal symbol:



AIP

Change target cycle for operation 01010100000200010 0010 Turning

Operation 0010 0010 Turning

Order	010101000002	Target qty.	50 PCE
Article	0101H34729-0010	Yield	70 PCE
Handle		Scrap	0 PCE
		Completion	140%

Workplace 01011004 Turning

Current status	PRODUCTION	Part.	2
for	2017-02-22 10:21:43	Current target cycle	5.000 [Sec./cycle]
Duration	9288:23:12	Act. cycle	0.000 [Sec./cycle]

New target cycle [Sec./cycle]

Staff badge number

mpcv 8.

18-03-16 10:45:09