

1 MOC Layout Configuration

1.1 Changing the size of detail applications

You can change the size and place of each detail application using drag and drop in the space reserved for the detail applications.


To change the size, move the mouse pointer to the edge of an application, click and hold the mouse button, drag the application to the required size and then release the mouse button.

1.2 Docking

You can place the detail applications next to or below each other or you can dock them. The term "Docking" results from the fact that separate applications are always docked to either the edge of a (main) application or next to or above each other, i.e. a single detail application always has a reference to the related main or affiliated application.

By activating the MES Development Suite, the docking mechanism is automatically activated. Using this mechanism, you can place the detail application where you like using drag and drop. Click the title bar of a detail application, hold the mouse button and move the mouse.

The mouse movement releases the current docking state of the application and the available docking options are shown by arrow symbols (see screenshot). If the released application is now moved towards one of the symbols, a color change indicates the effect of a shift. When you release the mouse button, the detail applications will dock at the required location.



You can use other detail applications or the main application as possible docking locations. A special feature is provided by the icon for "tabbing" detail applications, where applications are placed one above the other. You then use the tabs to display a detail application in the foreground.



From a technical point of view, it is generally possible to arrange detail applications "undocked" or "floating", but these detail applications will then leave the "context" of the MOC and are treated as separate windows by Windows. For this reason, the undocked detail application is not recommended.




When you create a docking configuration, you must configure the location with reference to the lines because if you change the size of the main application, the detail applications are changed accordingly (this is important when you change to the "maximize" window mode). See the examples below:


Example 1: Docking in a multi-line application

The following example describes how a multi-line docking configuration is created and how it can be used, for example, in the application *Workplace overview*.


Step 1: Detail application 1 is always docked to the selection panel of the main application.




Step 2: In the example, detail application 2 must be displayed to the right of detail application 1. For this reason, it is docked to the right of the detail application. An invisible "virtual docking panel" opens that includes both applications. This virtual docking panel makes sure that both detail applications always have the same height – this is then called a line with detail applications.



Step 3: You want to display detail application 3 below the existing applications. For this reason, it is docked to the bottom of the "virtual docking panel".




Step 4: Detail application 4 is again docked on the right hand side of detail application 3. Another "virtual docking panel" is created that ensures the correct height of detail applications 3 and 4.




Step 5: You want to customize detail application 5 as "tabbed detail application" with detail application 4. To generate tabbed detail applications, new detail applications are simply dragged "into" an existing application.


Tabbed detail applications behave like single applications if their size is changed. As many detail applications as required may be tabbed.



Step 6: A new line is generated - the new detail application is docked to the "virtual docking panel" of the second line and, as a result, the next detail application is docked to the right of it into the new, third line.




Step 7: The third line is to include three detail applications next to each other. The third application is docked to the right of the second application, and as a result, automatically to the "virtual docking panel" of the third line.



This results in an application that is docked line by line. The height of the rows can be changed at the marked positions.

The MOC provides a mechanism for changes of size. If the size of a detail application is changed, the detail applications at the bottom automatically change their size, too, and empty spaces are avoided.


The empty space shown in the picture on the right is filled automatically when the size of the application is changed.




Example 2: Docking in an application with detail applications of different heights

The next example shows how an application is created that includes detail applications with different heights. The activity calendar is an example for such an application.


Step 1: Detail application 1 is docked to the selection panel of the main application.



Step 2: Detail application 2 is docked to the right of detail application 1. This results again in a "virtual docking panel" that includes the two detail applications.




Step 3: Detail application 3 is docked *inside* of detail application 1 to the bottom. This generates another "virtual docking panel" at the location where detail application 1 has been before. This "virtual docking panel" now includes detail application 1 and detail application 3 and together with detail application 2 it also represents the content of the first "virtual docking panel".



The **result** is an application where you can change the height of the lines at the highlighted points.

The next time sizes are changed, the free space below the applications is automatically filled so that the two lower applications fully use it.



1.3 Simple customization of table views

Most applications use table views ("grids") to display data. Tables have several columns. The columns are grouped in so-called categories.

Show and hide columns and categories

Using drag and drop, you can move columns within categories and you can move the entire categories. Any user can individually make this kind of changes for any table view in any application.

You can also use the layout configuration to remove columns and categories or show hidden columns and categories using the context menu (right-click the column header to open the context menu).




If you want to show a column of a hidden category, you must first show and add the category to the table.

Filtering table results

In the grid, you can filter by specific values in the columns. Just click the pin next to the column header. A selection list of all values in this column is shown. This is the same procedure as filtering in MS Excel.

If you have set a filter for a column, this filter is displayed at the bottom left of the grid. Click the checkbox to delete the filter. You can edit and refine the filter subsequently. For this purpose, the button "Edit filter" is shown at the bottom right of the grid. Click to open the window with the filter editor. Optionally, you can open the filter editor using the function *Filter editor* in the context menu. In the dialog, you can select columns and specify comparison operators and values for each column.



Red text: if you click the red text, a list of possible link methods for several filters is shown.


Blue text: A list of columns included in the grid is shown. You can define a filter for these columns.

Green text: The list of available comparison operators for a filter is shown.

Plus: A new filter is added.

Cross: The relevant filter is removed.

You can subsequently extend an existing filter. The column of the column header, which has been clicked to show the dialog, is always suggested as comparison value.




Filters entered once are saved and can be called again. You can therefore create a list of filters. When the list has been stored in the customization level "Local", the list can be distributed to the users.

1.4 Customization of symbols

You can not only translate label texts, but you can also replace MOC symbols. You only need to store an image file with the required name and in a format that is supported (PNG, JPG, ICO) in the folder %scope%/resources/images.

You can identify the symbols and images used and their names using the dialog *Selected icons*. Example: To replace the "ApplicationLogo" icon, an image file with precisely this name must be stored in the "resources" folder.



Most symbols are available in the resolutions 32x32 (xxxLarge) and 16x16 (xxxSmall). The table below shows some exceptions.

Symbol / image	Name	Resolution
Start screen (splash screen)	splash.jpg	480x285
MOC logo (taskbar on the bottom right)	Logo.png	69x25
Start button (taskbar on the bottom left)	StartButton.png	104x20



If an image has a different resolution than the one mentioned above, unwanted effects in the display can occur, for example on the MOC desktop.

You can use the MOC "Update Package Creator" ([Extras](#) → [Generate Update Package](#)) to create update packages with own icons. This update package can be loaded in the Maintenance Manager and distributed to all clients of the system.