


1 Requesting Absences on the Terminal

Overview

Employees can use this function to request, change and delete absences on the PZE or BDE terminal. The terminal also provides an overview for the employee that displays the former requests and their request status.

Operation on the terminal

To start the absence planning on the PZE terminal, select the respective button and scan the badge. The following dialog opens and shows the requested, approved or planned absences.



Date from	Date till	Absence reason	Status
05.06.2012	05.06.2012	Urlaub	requested
14.06.2012	15.06.2012	Dienstreise	planned

On the BDE terminal, the dialog opens directly when you have pressed the respective button. To show the absences, you must first scan the badge. You cannot enter the staff badge number via keyboard. For security reasons, you must scan the badge via badge or bar code reader.

Note:

You can only use the function, if the terminal is online. If the terminal is offline, the request is canceled and an error message is output.

The list only shows planned absences of the future and the absence reasons that you can also request or plan on the terminal. The following statuses are shown:

Status	Description
requested	The absence has been requested, but has not yet been approved or refused.
approved	The absence has been requested and has been approved by the superior.
planned	The absence does not require approval and has been planned on the terminal or on the HYDRA client.



The list does not show the rejected requests. This way, the employee is not reminded again and again that they actually wanted to be off at a different time and that this request has been refused. The information that an absence request has been refused is shown when the employee clocks in or out on the PZE terminal (AIP or ctwin).

Function key assignment

Cancel

Use this button to close the dialog.


Request

To request an absence, the following dialog opens (P_FZP_INS):

Select an absence reason and enter a period. Click the button **OK** to request or plan the absence. You can also enter a comment.


Edit

The employee can use the dialog *Edit absence* (P_FZP_UPD) to change a planned absence. This function is only available for absences that need not be approved:



Delete

The employee can use the dialog *Delete absence* (P_FZP_DEL) to delete a planned or requested absence. If an absence has been requested, the superior is informed that the request has been canceled:





The button *Delete* is only available for the following absences:

- requested and not yet approved absences;
- absences that do not require approval;
- absences that have been entered on the terminal.

Info

The employee can use this button to display the current account balances. The same display is shown if you press the *Info* button on the PZE terminal:

Information [00002006]		[#0009]	
	Designation	Value	
	Flextime	0:00	
	Overtime	0:00	
	Flex. time	0:00	
	Leave Account	0.00	
Cancel OK			

Terminal configuration

On the PZE terminal, the functionality described can be enabled using an *Absence reason* button. In the terminal configuration, tab *HR functions*, assign the entry "_FZP" to one of the fields *Absence reason 1* to *Absence reason 4*. You can define the label text of the respective button on the PZE terminal in one of the fields *Absence reason text 1* to *Absence reason text 4*.

On the BDE terminal, you can enable the functionality using the dynamic dialog P_FZP. The following entry is made in any section of the INI file ctaipbut.ini:

X=P_FZP,R,*button label* (X = button index)

Activating dynamic dialogs

To call the dialog on the terminal, the dynamic dialog *P_FZP* must be enabled. The dialog is usually enabled during installation of the system. If this is not the case, you can enable the dialog in the application [Dynamic dialogs](#) using the button *Activate dialog*.



You can define dynamic dialogs for terminals or terminal groups. This option is mainly used on BDE terminals. If you want to use the absence workflow on a terminal where dialogs for the terminal or the terminal group exist, you must copy and enable the dialogs *P_FZP*, *P_FZP_INS*, *P_FZP_UPD* and *P_FZP_DEL* for the terminal or the terminal group.