

1 Room Zones

Summary

Menu	Master data → Access control → Room zones
Transaction code	rozo
Function authorization	rozo

Room zones can be used to verify whether or not employees are present in specific rooms or areas. Room zones can be entered and exited using access points. This can be configured along with the [access points](#).

Validation checks may be enabled to make sure that an employee may only enter a room zone if he/she is not already present or may only leave it if he/she is already present.

A maximum occupation rate can be defined for room zones. Consequently, employees might be rejected if the parking lot is full, for instance.

Room zone	Designation	Responsibility area
1	Admin. Building	
2	Basement Parking	
3	Production Hall	

Room zone: 1 ... Admin. Building

Responsibility area:

Options:

- ☐ Plausibility check when entering
- ☐ Plausibility check when exiting
- ☒ Log attendance in room zone

Maximum occupancy:

Maximum occupancy:

Channel for max. occupancy:

Last editing:

Modified by: Miller

Modified on: 6/9/2004 4:56:11 PM

Two requirements need to be met to be able to use room zones:

1. Both, the entries and the exits need to be controlled by access control.
2. It has to be ensured that all employees log in and out individually at the entries and exits. This can either be realized by an organizational or technical approach (e.g. turnstiles).

Field description

Room zone, designation

Number of the room zone and its name

Responsibility area

Responsibility area which the room zone is assigned to. The responsibility area is checked when editing this configuration and, in addition, it is also verified whether or not the "use" authorization is available when room zone assignments are created, changed and deleted within the [room zone overview](#).

Validation checking upon entry, validation checking upon exit

These two options specify whether the entrance into the room zone is denied if the badge is already present in the room zone or whether the exit from the room zone is denied if the badge is not present in the room zone.

Log attendance in room zone

By this option, past periods when an employee was present in the room zone can be recorded. These logs can be viewed using the [room zone overview](#). If logging is disabled, the room zone overview only shows the currently present employees and these entries are deleted when the employee exits the room zone.

Maximum occupancy

The maximum number of employees that may be present in the room zone can be configured here. Any further access attempt will be rejected and recorded including the reason "Room zone completely occupied" within the [access log](#), once this maximum number has been exceeded.

Channel for max. occupancy

The channel specified here is triggered at the ZKS terminal if the maximum number of employees that may be present in the room zone has been reached. This channel can trigger, for example, lights (red/green traffic lights).