

1 Production Variants/Methods

Available methods

Method	Usage
FERTVAR.INSERT	Create a production variant/method
FERTVAR.UPDATE	Change a production variant/method
FERTVAR.DELETE	Delete a production variant/method

Data

Column	Description
Field	Field name
V (usage)	S Key field clearly identifying the data record. (Further key fields might be required). The field must be completed.
T (type)	Data type of the field
L (length)	Field length For fields of data type DEC: Overall number of digits without decimal separator and algebraic sign
D (decimal places)	For fields of data type DEC: Number of decimal places; otherwise: not relevant
Description	Description and/or comment of the field

Field	V	T	L	D	Description
FERTVAR.VER	S	CHAR	10		Version
FERTVAR.ATK	S	CHAR	40		Article
FERTVAR.ATK:BEZ		CHAR	40		Article name
FERTVAR.MNR	S	CHAR	8		Workplace
FERTVAR.MGRP	S	CHAR	8		Group
FERTVAR.FIR:ATK	S	CHAR	10		Company for article
FERTVAR.RESTYP		CHAR	8		Resource type
FERTVAR.WANZ		NUMC	9		Number of resources
FERTVAR.RES		CHAR	20		Resource
FERTVAR.PRIO		NUMC	9		Priority
FERTVAR.SZY		NUMC	9		Target cycle (in seconds/1000 cycles)
FERTVAR.SZY:ABW		DEC	5	2	Admissible deviation
FERTVAR.TLG		NUMC	9		Partitioning
FERTVAR.RUEZ		NUMC	9		Setup time
FERTVAR.ABRZ		NUMC	9		Teardown/retooling time
FERTVAR.DATB		DATE			Valid from
FERTVAR.DATE		DATE			Valid until
FERTVAR.STA		CHAR	1		Status "F" Released "S" Blocked
FERTVAR.GRTXTNR		NUMC	4		Blocking reason

Field	V	T	L	D	Description
FERTVAR.BEM		CHAR	40		Comment
FERTVAR.USRFLD		CHAR	8		User field key
FERTVAR.FU:1		DATE	10		User field 1
FERTVAR.FU:2		DATE	10		User field 2
FERTVAR.FU:3		DATE	10		User field 3
FERTVAR.FU:4		DATE	10		User field 4
FERTVAR.FU:5		DATE	10		User field 5
FERTVAR.FU:6		DATE	10		User field 6
FERTVAR.FU:7		NUM	8		User field 7
FERTVAR.FU:8		NUM	8		User field 8
FERTVAR.FU:9		NUM	8		User field 9
FERTVAR.FU:10		NUM	8		User field 10
FERTVAR.FU:11		NUM	8		User field 11
FERTVAR.FU:12		NUM	8		User field 12
FERTVAR.FU:13		NUM	8		User field 13
FERTVAR.FU:14		NUM	8		User field 14
FERTVAR.FU:15		NUM	8		User field 15
FERTVAR.FU:16		NUM	8		User field 16
FERTVAR.FU:17		NUM	8		User field 17
FERTVAR.FU:18		NUM	8		User field 18
FERTVAR.FU:19		NUM	8		User field 19
FERTVAR.FU:20		NUM	8		User field 20
FERTVAR.FU:21		NUM	8		User field 21
FERTVAR.FU:22		NUM	8		User field 22
FERTVAR.FU:23		DEC	13	3	User field 23
FERTVAR.FU:24		DEC	13	3	User field 24
FERTVAR.FU:25		DEC	13	3	User field 25
FERTVAR.FU:26		DEC	13	3	User field 26
FERTVAR.FU:27		DEC	13	3	User field 27
FERTVAR.FU:28		DEC	13	3	User field 28
FERTVAR.FU:29		CHAR	1		User field 29
FERTVAR.FU:30		CHAR	1		User field 30
FERTVAR.FU:31		CHAR	1		User field 31
FERTVAR.FU:32		CHAR	1		User field 32
FERTVAR.FU:33		CHAR	1		User field 33
FERTVAR.FU:34		CHAR	1		User field 34
FERTVAR.FU:35		CHAR	1		User field 35
FERTVAR.FU:36		CHAR	1		User field 36
FERTVAR.FU:37		CHAR	1		User field 37
FERTVAR.FU:38		CHAR	1		User field 38
FERTVAR.FU:39		CHAR	1		User field 39
FERTVAR.FU:40		CHAR	1		User field 40
FERTVAR.FU:41		CHAR	1		User field 41
FERTVAR.FU:42		CHAR	1		User field 42
FERTVAR.FU:43		CHAR	1		User field 43
FERTVAR.FU:44		CHAR	1		User field 44
FERTVAR.FU:45		CHAR	10		User field 45
FERTVAR.FU:46		CHAR	10		User field 46

Field	V	T	L	D	Description
FERTVAR.FU:47		CHAR	10		User field 47
FERTVAR.FU:48		CHAR	10		User field 48
FERTVAR.FU:49		CHAR	10		User field 49
FERTVAR.FU:50		CHAR	10		User field 50
FERTVAR.FU:51		CHAR	20		User field 51
FERTVAR.FU:52		CHAR	20		User field 52
FERTVAR.FU:53		CHAR	20		User field 53
FERTVAR.FU:54		CHAR	20		User field 54
FERTVAR.FU:55		CHAR	20		User field 55
FERTVAR.FU:56		CHAR	20		User field 56
FERTVAR.FU:57		CHAR	20		User field 57
FERTVAR.FU:58		CHAR	20		User field 58
FERTVAR.FU:59		CHAR	20		User field 59
FERTVAR.FU:60		CHAR	20		User field 60
FERTVAR.FU:61		CHAR	20		User field 61
FERTVAR.FU:62		CHAR	20		User field 62
FERTVAR.FU:63		CHAR	20		User field 63
FERTVAR.FU:64		CHAR	20		User field 64
FERTVAR.FU:65		CHAR	40		User field 65
FERTVAR.FU:66		CHAR	40		User field 66

Information on key fields:

The fields "group" (FERTVAR.MGRP) and "workplace" (FERTVAR.MNR) can be entered separately or together. But one of the two values must be entered in any case.