

1 Messages to Employees

Summary

Menu	Master Data --> People --> Messages to Employees
Transaction Code	pmes
Function authorization	pmes

The "messages to employees" function makes it possible to display any texts, when people try to post something at the terminal. In this way, people may be asked, for example, to contact the payroll office or they may be reminded of closing doors and windows or shutting down machines on the last working day of the week

The screenshot shows the 'Messages to employees' application window. The window has a title bar 'Messages to employees' and a menu bar with 'Main page' and 'Profile'. Below the menu bar is a toolbar with icons for 'Request data', 'Cancel', 'Print preview', 'Print all', 'Insert', 'Copy', 'Edit', 'Delete', 'Save', and 'Help'. The main area is divided into two panes. The left pane, titled 'Messages to employees', contains a table with columns: 'Personnel selection', 'Com...', 'Personnel selection', 'Value', 'Name', 'Valid from', 'Valid until', and 'Q...'. The table has three rows: 0001, BSP, and 0001. The right pane, also titled 'Messages to employees', contains a 'Personnel selection' section with a 'Company' dropdown (0001) and a 'Personnel selection' dropdown. Below this is a 'Message' section with fields for 'Valid from', 'Valid until', 'Quantity', 'Event', and 'Message'. The 'Message' field contains the text 'Gong Xi Fa Xai!'. At the bottom right is a 'Clocking status' section with checkboxes for 'In', 'Out', 'Break', 'Absence reason', and 'Information'.

Utilization



Messages are sent in periodic intervals to the terminals so that a specific time passes until they are displayed on the terminals. The configuration is made within the PZE properties of the [terminal configuration](#). The "display duration of info" field specifies how long the messages are displayed at the terminal.



Not more than 20 characters may be entered per message line for terminals the display is 20 characters long (e.g. CT-370).

The terminals of the type CTP-340 or terminals by Kaba Benzing do not support the display of messages function.

Field Descriptions in the "message" tab

Company

Restricts the validity of the clocking authorization to a specific company.

Personnel selection

The next two fields allow for the "clocking authorization" to be restricted to a specific person or group of people. The HR master fields "cost center", "area", "employee subgroup", "activity" and "staff membership" may be selected as employee groups.

Valid from, to

Validity period of the message

Number

Specifies how often a message is to be displayed for a person at the terminal. If the field is left empty the message is shown without any restriction. When a message is changed, it is impossible to change the number, as otherwise it cannot be traced back how often individual people have already read the message.

Message

Message that is to be displayed at the terminal.

Clocking status

It may be defined for which clocking statuses messages are to be displayed for the person.

Field descriptions of the "validity" tab

Weekday

It may be selected at which weekdays the message is to be displayed.