

1 Manual BSC identification

Persons/Staff

You can identify the number of active persons/staff in the system using the application "HR master data":

Menu	Master data → Staff → HR master data
Transaction code	pers
Function authorization	Pers

A person is considered active if the following requirements are fulfilled:

- The current date is between the date "Valid from" and the date "Valid to".
- The person has joined but not yet left the company on the current date.
- The person is not locked for time and attendance.

Here, you can find this information in the HR master data:


✓
✗
Edit

Main page

Person
Personal data
Shop floor data
Incentive wage
Time and labor data
Additional info

Person

Person 40563

Valid from 13.06.2015 Valid to

Staff badge no. 4563

Name

Title

First name Mary

Last name Green

Assignment

Company BSP

Area LLE

Cost center 105

Department Akk

Employee subgroup

Activity Packing

Responsibility area 105

Staff membership

Date of joining 11.08.1993 Date of leaving

Supervisor

Supervisor 50201 Meyers, Harald Edward

The screenshot shows a software interface for editing HR master data. The window is titled 'Edit' and has a 'Main page' header. Below the header are several tabs: 'Person', 'Personal data', 'Shop floor data', 'Incentive wage', 'Time and labor data' (which is selected), and 'Additional info'. The 'Time and labor data' tab contains four sections:

- Models:** Contains four rows of data:
 - Working time model: 200 ... 3-Shift
 - Shift rhythm model: 201 ... 3-Shift Afternoon
 - Payment model: 200 ... 3-Shift
 - Overtime type: 0 ...
- Basic data:** Contains several fields:
 - Employment relationship: ☒ Salaried, ☐ Non-salaried
 - Average working time: 0:00
 - Part-time rate: 0,000 %
 - First allocation: [dropdown]
 - Date of latest evaluat.: 04.03.2015
 - Time sheet: [dropdown]
- Leave entitlement:** Contains three rows of data:
 - Annual leave: 30,0
 - Special leave: 2,0
 - Additional leave: 0,0
- Options:** Contains four checkboxes:
 - ☐ Business trip authorization
 - ☒ Lock person (highlighted with a red box)
 - ☐ Person does not clock
 - ☐ Allocate average working time

The systems checks the information when a new active version of the HR master data is created and when a valid HR master data version is changed from inactive to active. The check is performed after manual maintenance and after an interface run of the HR master data interfaces.

Workplaces

You can identify the number of active workplaces/machines in the system using the application "Workplace and resource configuration": Filter by resource type "MNR":

Menu	Master data → Resources → Resource configuration Master data → Workplaces/machines → Workplace configuration
Transaction code	Res
Function authorization	Mdres mdresgenh for fields in connection with Test Equipment Management

A workplace or a machine is considered active if it is not "Blocked" in the "Workplace configuration".

The screenshot shows the 'Workplace configuration' dialog box in SAP. The 'Blocked' checkbox is highlighted with a red rectangle. The dialog box is divided into three sections: 'Workplace master data', 'Entry', and 'Posting'.

Workplace master data

- Workplace category: N Machine ☒ Blocked
- Workplace type: E Single user workplace ☐ External workplace
- Comp.:
- Group: ASSEMBLY
- Category:
- Year model: 5 ...
- Standard rate machine: 20,00 EUR
- Standard labor rate: 10,00 EUR
- Performance level: 100 %
- Incentive wage indicator: Z Time wage
- File name:

Entry

- Logon of several OPs: J Yes, any number of operations
- Sequencing list: S Basic settings
- Number of OPs in sequencing list: 500
- Compulsory sequence: N Inactive
- Display 3rd list: Input material
- Show mat./PRT list when logging OP on: N No
- Dialog control:

Posting

- Quantity posting to staff: N None ☒ Posting on OPs that are not logged on
- Posting of machine time for parallel OPs: N No proportionate posting

DNC machines

You can identify the number of active DNC machines in the system using the applications "Assignment of DNC family to machine" and "Workplace and resource configuration":

Menu	Master data → Resources → Assignment of DNC family to machine
Transaction code	Dncmas
Function authorization	mddncma.*

A DNC machine is considered active, if the following requirements are fulfilled:

- An entry is made for the machine in the application "Assignment of DNC family to machine"
- The machine is not "Blocked" in the "Workplace and resource configuration".

Logical channels

You can identify the number of logical channels within the system using the application “PDV - logical channels”.

Menu	Master data → Process data processing → Logical channels
Transaction code	lgchcnf
Function authorization	lgchcnf.*

The system takes into account all logical channels that have been created.