

1 Advanced Batch Information

Usage

You use the function to view information on a batch at the AIP terminal. Advanced batch information includes:

- General batch information
- Quantities
- Batch attributes
- Alternative batch numbers

Dialog configuration

Dialog configuration (LOS INFOS)

Define the AIP function key in the file **ctaipbut.ini**:

```
[ANR-LN-Page3]
```

```
1=LOS_INFOS,L,Losinformation,Shipping Box Closed Information.png
```

The sections [LOS_INFOS_ATTR.LST] and [LOS_INFOS_QUA.LST] and [LOS_INFOS_ALTER.LST] are required in the layout configuration of **ctaisplay.ini**:

```
[LOS_INFOS_ATTR.LST]
```

```
GRID_FONT=Arial
```

```
GRID_FONTSIZE=9
```

```
GRID_COLOR=clBlack
```

```
GRID_BACKGROUND=clWhite
```

```
KENNUNG=C20,100,L,Attribute
```

```
ATTR_VAL=C20,80,L,Value
```

```
EINH=C20,80,L,Unit
```

```
TXT=C20,80,L,
```

```
MATTYP=C40,140,
```

```
[LOS_INFOS_QUA.LST]
```

```
GRID_FONT=Arial
```

```
GRID_FONTSIZE=9
```

```
GRID_COLOR=clBlack
```

```
GRID_BACKGROUND=clWhite
```

```
KENN=C20,100,L,
```

```
ALIAS LEER1=(DUMMY1)=C1,30,L
```

```
MENGE=C20,80,R,
```

```
EINH=C4,40,R,
```

```
ALIAS LEER2=(DUMMY1)=C1,30,L
```

```
REST=C20,80,R,
```

```
[LOS_INFOS_ALTER.LST]
```

```
GRID_FONT=Arial
```

```
GRID_FONTSIZE=9
```

```
GRID_COLOR=clBlack
```

```
GRID_BACKGROUND=clWhite
```

```
ALT=C20,100,L,
```

```
CNR=C20,200,L,
```

System configuration

Further system configurations are not required to display advanced batch information.