



PORTRAIT 1200 x 1800 px = 4.00 in x 6.00 in @ 300 DPI

Yellow: QR code, 300 px (1.00 in) square at x=820, y=1400. Leave it as plain background: the booth puts the QR here on prints and your logo file on downloads and stories.

Red edge (outer 36 px) may be trimmed: fill it with background art, no white.

Dashed line (70 px in): keep text, faces and logos inside it.


QR / LOGO
300 px






Portrait frame, drawn at 6.2 x 9.2 in

Draw over the light-blue lines (they scan out). Fill art to the outer border. Scan the whole page at 600 DPI.





LANDSCAPE 1800 x 1200 px = 6.00 in x 4.00 in @ 300 DPI

Yellow: QR code, 240 px (0.80 in) square at x=1490, y=890. Leave it as plain background: the booth puts the QR here on prints and your logo file on downloads and stories.


Red edge (outer 36 px) may be trimmed: fill it with background art, no white.

Dashed line (70 px in): keep text, faces and logos inside it.

QR / LOGO
240 px

Landscape frame, drawn at 10.0 x 6.7 in

Draw over the light-blue lines (they scan out). Fill art to the outer border. Scan the whole page at 600 DPI.



EVENT NAME drawn by the app (shows your event name)

INSTRUCTIONS PANEL

drawn by the app (title and the 4 steps)

HOME SCREEN 1024 x 600 px. This template is 2048 x 1200 px (2x).

Save your art as home.png at either size.

Dark boxes: the app draws these on top of your art. Don't draw an event name, instructions or a start button.

The panel is see-through, so art behind it only shows faintly. Keep that area simple.

Guests tap anywhere to start. The art fills the whole screen, so draw to the outer edge.

Dashed line (30 px in): keep faces and logos inside it.

The panel and button are dark purple with a neon glow, so a dark background keeps them readable.

TAP TO START

Home screen, drawn at 10.0 x 5.9 in

Draw over the light-blue lines (they scan out). Fill art to the outer border. Scan the whole page at 600 DPI.

