Running, checking and saving an analysis

Controls: Run Analysis; (?); Show regression configuration; Display Coefficient Chart; Display Instrument Map; Map Size; Presentation view; downloads.

1. Run and inspect the chosen specification. Choose the settings and press Run Analysis to estimate the model. Changing an estimation setting does not by itself replace the previous result. Run again before interpreting or downloading the revised specification. A question-mark button displays a one-page explanation. Open PDF opens the document separately; Download PDF saves it. Use PDF viewer switches to the browser's PDF display. Where several notes apply, Related explanations lets you choose another note. Opening help does not change the model settings.

Show regression configuration reveals the settings used for the displayed result, including years, instrument construction, controls, fixed effects and sample restrictions. The button then changes to Hide regression configuration. This display helps check that a comparison changes only the intended settings. The data-notes section explains coverage and sample exclusions. Neither display changes the regression.

2. Read the chart and map. Display Coefficient Chart shows the main coefficient from each reported model, with conventional 95 percent Wald confidence intervals. The vertical zero line helps assess whether the interval includes zero. These intervals use the chosen standard-error method; for IV estimates they are not protected against weak instruments. A first-stage chart shows the instrument coefficient, rather than the productivity effect.

Display Instrument Map shows an available precomputed historical density map. It is not a map of estimated productivity effects. The map displays density in levels before regression controls and sample exclusions, even when the regression uses a logged instrument. Maps are unavailable for State instruments, population-total instruments and the 1870–1900 instruments. An unavailable map does not mean estimation is unavailable. Map Size changes the image width; Presentation view changes the display layout. Neither changes the estimates.

3. Save coefficients or the full result. Coefficients (CSV) saves a table that can be opened in a spreadsheet or statistical program. It contains coefficient estimates and uncertainty measures, together with specification information. Results (HTML) saves a browser-readable document containing the results table, coefficient chart, selected specification and relevant notes. These downloads describe the last successful analysis. Chart (PNG), available when the chart is displayed, saves the coefficient figure as an image.

4. Inspect the linked county regression. County calibration (CSV) is available for county-adjusted CH. It reports the linked county regression's coefficients, standard errors, sample size and settings, excluding individual state fixed-effect coefficients. A separate field identifies the geography coefficients transferred into the aggregate CH index. The county density coefficient and optional county-area coefficient are reported for inspection but are not transferred. The download contains regression output, rather than the underlying county-level observations.