



## Lab sheet 03


1)



2)



3)



```
Router0
Physical Config CLI
IOS Command Line Interface

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>en
Router>enable
Router#configure t
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#inter
Router(config)#interface fa
Router(config)#interface FastEthernet 0/0
Router(config-if)#ip
Router(config-if)#ip a
Router(config-if)#ip ad
Router(config-if)#ip address 192.168.11.100 255.255.255.0
Router(config-if)#no
Router(config-if)#no shu
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state t
o up

Router(config-if)#exit
Router(config)#inter
Router(config)#interface ser
Router(config)#interface serial 2/0
Router(config-if)#ip ad
Router(config-if)#ip ad
% Incomplete command.
Router(config-if)#ip ad
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#no sh
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#exit
Router(config)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to down

Copy Paste
```



```
Router1
Physical Config CLI
IOS Command Line Interface

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>en
Router#config
Router#configure t
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#inter
Router(config)#interface fa
Router(config)#interface FastEthernet 0/0
Router(config-if)#ip ad
Router(config-if)#ip address 192.168.11.100 255.255.25.0
Bad mask 0xFFFF:100 for address 192.168.11.100
Router(config-if)#ip ad
Router(config-if)#ip address 192.168.11.100 255.255.255.0
Router(config-if)#no shu

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state t
o up

Router(config-if)#no shu
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#inter
Router(config)#interface ser
Router(config)#interface serial 2/0
Router(config-if)#ip ad
Router(config-if)#ip address 10.0.0.2 255.0.0.0
Router(config-if)#no sh
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Router(config-if)#exit
Router(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Copy Paste
```

