
How to configure and use the countdown template

What you'll need

Two ArcGIS.com web maps:

- Overview web map
 - o To be displayed at a smaller scale.
 - o This map must contain the points (content layer) represented in the template's list view.
 - o Popups for the content layer will be displayed in the left hand panel.
- Close up (or large scale) web map
 - o To be displayed at a larger scale.
 - o Provides a close up view of an individual feature from the overview map's content layer.
 - Popups for the close up map will not be honored (this may change)
 - o Close up map may contain layers, but can also just be a base map



Note: By design, these two maps can swap positions. And in fact, the overview map initially appears on the right, not the left (as pictured here).

Configuration

- 1) Download application files and deploy in a web server directory (or virtual directory).
- 2) Open config.js and supply:

| | - |
|----------------------------|---|
| webmap_largescale | Web map id for close up web map |
| webmap_overview | Web map id for overview web map |
| contentLayer | Name of the overview map's content layer as it appears in the |
| | ArcGIS.com viewer TOC. |
| fieldName_Rank | Field name in the content layer to be used for the numbers on |
| | the side (this may be going away). Must be integer values. |
| fieldName_Name | Designates the name of the content feature. |
| fieldName_Level | (optional) Field containing integer values. For each feature, |
| | specifies zoom level at which large scale map should be |
| | displayed. If this field isn't specified, the app will simply use |
| | the defaultLargeScaleZoomLevel setting below. |
| initialZoomLevel | Zoom level at which to display the overview map initially (this |
| | may be going away in favor of just using the web map setting) |
| initialZoomLevelWide | Initial zoom level for overview map when app window has a |
| | wider aspect ratio (this may be going away) |
| defaultLargeScaleZoomLevel | Zoom level at which to present the large scale map whenever a |
| | feature is selected. |
| showIntro | Indicates whether to show the intro screen at start-up. |
| popupHeight | How much vertical space (in pixels) should be allotted for the |
| | popup display in the left hand pane. At the moment, this |
| | cannot be calculated automatically. |
| popupLeftMargin | How much white space (in pixels) should be inserted in the left |
| | margin of the popup view. |

