Homework 1

Due Date: By the end of Friday, 2/3/2023.

Total points: 100

There are six (6) questions.

Submit your work in a PDF file in HuskyCT.

Some answers are provided. You need to show how you find out the answers.

Practice converting small numbers (< 10,000) without a calculator.

Always write brief comments in your code.

- 1. For each of the 10-bit numbers specified by hexadecimal digits below, write down 1) the 10 bits in the number, 2) its value in decimal when the bits are interpreted as 10-bit unsigned binary numbers, and 3) its value in decimal when the bits are interpreted as 10-bit two's complement numbers.
 - a. 0x 1AB
 - b. 0x 2CD
- 2. Convert the following decimal numbers to 8-bit 2's complement numbers, and then represent 8 bits with two hexadecimal digits.
 - a. 95
 - b. -101

Continued on the next page.

3. For each instruction in the table, write 8 hexadecimal digits that represent the 32 bits in the destination register after the instruction is executed.

Assume s0 is 0x98ABCD6A, s1 is 0x20FF5A98.

Find out the answers by working on bits/hexadecimal digits. Do not convert large numbers from hexadecimal to decimal.

Instructions				Dest. reg. in 8 hexadecimal digits
add	t0, s	s0,	s1	
and	t1, s	s0,	s1	
or	t2, s	s0,	s1	
xor	t3, s	s0,	s1	
addi	t4, s	s0,	0x2FA	
andi	t5, s	s0,	-16	
slli	t6, s	s0,	12	
srai	s2, s	s0,	8	

4. Write RISC-V instructions to perform the operations in the following pseudocode on register s1. Note that bits 8 to 0 in s1 are not changed. For example, if s1 is 0x5555E3AB, it will become 0x000001AB. If s1 is 0x5555ECAB, it will become 0xFFFFEAB. Use temporary registers like t0 and t1 to save intermediate values. Since we are dealing bits, it is more convenient to write immediate in hexadecimal.

```
IF bit 9 of s1 is 1

Set bits 31 to 9 of s1 to 0

ELSE

Set bits 31 to 9 of s1 to 1
```

5. The following RISC-V instructions calculate the Hamming weight (the number of 1's) of s0. The result is saved in register s1.

```
addi s1, x0, 0
                             # s1 = 0
      addi t0, x0, 1
                             # Use t0 as mask to test each bit in s0
loop:
           t1, s0, t0
                            # extract a bit with the mask
     and
           t1, x0, skip # if the bit is 0, do not increment s1
     beg
     addi s1, s1, 1
                             # increment the counter
skip:
     slli t0, t0, 1
                        # shift mask to left by 1
      bne t0, x0, loop # if the mask is not 0, continue
```

- a. If s0 is 0xFF00FF00, how many instructions are executed? Does the number of executed instructions depend on the number of 1's in s0? Does it depend on the location of 1's? Explain your answers.
- b. There are many ways to compute Hamming weight. We could test the most significant bit (bit 31) of s0. For example, extract bit 31 with an AND instruction, and compare it with 0. This is similar to the method in the code given. However, we can save one instruction. If we treat s0 as a 2's complement number, s0 is less than 0 if and only if bit 31 in s0 is 1. Using this method, write RISC-V instructions to compute the Hamming weight of s0. Explain your method in comments. We can start with the following two instructions. How many instructions are executed if s0 is 0xFF00FF00?

```
addi s1, x0, 0 \# s1 = 0 add t0, x0, s0 \# make a copy so s0 is not changed
```

Continued on the next page.

6. Translate the following C code to RISC-V assembly code. Assume that a, i, and r are stored in registers s1, s2, and s3, respectively. All the variables are signed. Write brief comments in your code. Clearly mark the instructions that control the loop (for example, using different colors), the instructions in if branch, and instructions in else branch.

Use a minimum number of instructions. There are 12 instructions in the solutions.

```
for (i = 0; i < a; i += 1)
   if ((i & 0x91) != 0)
       r ^= i << 8;
   else
      r += i >> 4;
```