

enable_grad#

https://pytorch.org/docs/stable/generated/torch.enable_grad.html#torch.enable_grad

Description:

Context-manager that enables gradient calculation. Enables gradient calculation, if it has been disabled via `no_grad` or `set_grad_enabled`. This context manager is thread local; it will not affect computation in other threads. Also functions as a decorator.

Function Signature

```
class torch.enable_grad(orig_func=None)[source]#
```

Example::

Code Examples

```
>>> x = torch.tensor([1.], requires_grad=True)
>>> with torch.no_grad():
...     with torch.enable_grad():
...         y = x * 2
>>> y.requires_grad
True
>>> y.backward()
>>> x.grad
tensor([2.])
>>> @torch.enable_grad()
... def doubler(x):
...     return x * 2
>>> with torch.no_grad():
...     z = doubler(x)
>>> z.requires_grad
True
>>> @torch.enable_grad()
... def tripler(x):
...     return x * 3
>>> with torch.no_grad():
...     z = tripler(x)
>>> z.requires_grad
True
```

Notes & Warnings

NOTE

Note `enable_grad` is one of several mechanisms that can enable or disable gradients locally see `Locally disabling gradient computation` for more information on how they compare.

NOTE

Note This API does not apply to forward-mode AD.

Detailed Documentation

Documentation

Context-manager that enables gradient calculation.

Enables gradient calculation, if it has been disabled via `no_grad` or `set_grad_enabled`.

This context manager is thread local; it will not affect computation in other threads.

Also functions as a decorator.

`enable_grad` is one of several mechanisms that can enable or disable gradients locally see [Locally disabling gradient computation](#) for more information on how they compare.

This API does not apply to forward-mode AD.

Context-manager that enables gradient calculation.

Enables gradient calculation, if it has been disabled via `no_grad` or `set_grad_enabled`.

This context manager is thread local; it will not affect computation in other threads.

Also functions as a decorator.

`enable_grad` is one of several mechanisms that can enable or disable gradients locally see [Locally disabling gradient computation](#) for more information on how they compare.

This API does not apply to forward-mode AD.
