

Totally Integrated Automation Portal

DB_External_Interface [DB100]

DB_External_Interface Properties

General

Name	DB_External_Interface	Number	100	Type	DB	Language	DB
Numbering	Manual						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Offset	Start value	Retain	Accessi-ble from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static										
▼ RB154	"RB_Interface"	0.0		False	True	True	True	False		
Occupied	Bool	0.0	false	False	True	True	True	False		
Empty	Bool	0.1	false	False	True	True	True	False		
Faulted	Bool	0.2	false	False	True	True	True	False		
ReadyToTransfer	Bool	0.3	false	False	True	True	True	False		
▼ RB159	"RB_Interface"	2.0		False	True	True	True	True		
Occupied	Bool	2.0	false	False	True	True	True	False		
Empty	Bool	2.1	false	False	True	True	True	False		
Faulted	Bool	2.2	false	False	True	True	True	False		
ReadyToTransfer	Bool	2.3	false	False	True	True	True	False		
▼ RB160	"RB_Interface"	4.0		False	True	True	True	True		
Occupied	Bool	4.0	false	False	True	True	True	False		
Empty	Bool	4.1	false	False	True	True	True	False		
Faulted	Bool	4.2	false	False	True	True	True	False		
ReadyToTransfer	Bool	4.3	false	False	True	True	True	False		
Heartbeat_PL_C_0	Bool	6.0	false	False	True	True	True	True		
Heartbeat_PL_C_2	Bool	6.1	false	False	True	True	True	False		
▼ Connection_PL_C_2	Struct	8.0		False	True	True	True	False		
Heartbeat_PL_C_1	Bool	8.0	false	False	True	True	True	False		
PL_C_1_Faulted	Bool	8.1	false	False	True	True	True	False		
RB157_Transfer	Bool	8.2	false	False	True	True	True	False		
RB157_Faulted	Bool	8.3	false	False	True	True	True	False		
RB158_Transfer	Bool	8.4	false	False	True	True	True	False		
RB158_Faulted	Bool	8.5	false	False	True	True	True	False		
▼ Connection_PL_C_0	Struct	10.0		False	True	True	True	False		
Heartbeat_PL_C_1	Bool	10.0	false	False	True	True	True	False		
PL_C_1_Faulted	Bool	10.1	false	False	True	True	True	False		
RB155_Transfer	Bool	10.2	false	False	True	True	True	False		
RB155_Faulted	Bool	10.3	false	False	True	True	True	False		