

Totally Integrated Automation Portal

FC_HMI_Interface_variables [FC108]

FC_HMI_Interface_variables Properties							
General							
Name	FC_HMI_Interface_variables	Number	108	Type	FC	Language	LAD
Numbering	Manual						
Information							
Title		Author		Comment	Mapping logic variables to HMI-specific variables.	Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
FC_HMI_Interface_variables	Void		

Network 1: Sesnsors declaration

```
0001 // TAB1
0002 "HMI_Transfer".Status.SNS.TAB1.High_level := "Transfer_DB".Tab1.SNS_TableTop;
0003 "HMI_Transfer".Status.SNS.TAB1.Middle_level := "Transfer_DB".Tab1.SNS_TableMiddle;
0004 "HMI_Transfer".Status.SNS.TAB1.Low_level := "Transfer_DB".Tab1.SNS_TableDown;
0005
0006 "HMI_Transfer".Status.SNS.TAB1.Presence1 := "Transfer_DB".Tab1.SNS_Presence1;
0007 "HMI_Transfer".Status.SNS.TAB1.Presence2 := "Transfer_DB".Tab1.SNS_Presence2;
0008
0009 // TAB2
0010 "HMI_Transfer".Status.SNS.TAB2.High_level := "Transfer_DB".Tab2.SNS_TableTop;
0011 "HMI_Transfer".Status.SNS.TAB2.Middle_level := "Transfer_DB".Tab2.SNS_TableMiddle;
0012 "HMI_Transfer".Status.SNS.TAB2.Low_level := "Transfer_DB".Tab2.SNS_TableDown;
0013
0014 "HMI_Transfer".Status.SNS.TAB2.Maserati := "Transfer_DB".ChainTransfer.SNS_MaseratiTab2;
0015 "HMI_Transfer".Status.SNS.TAB2.Presence1 := "Transfer_DB".Tab2.SNS_Presence1;
0016 "HMI_Transfer".Status.SNS.TAB2.Presence2 := "Transfer_DB".Tab2.SNS_Presence2;
0017
0018 // TAB3
0019 "HMI_Transfer".Status.SNS.TAB3.High_level := "Transfer_DB".Tab3.SNS_TableTop;
0020 "HMI_Transfer".Status.SNS.TAB3.Middle_level := "Transfer_DB".Tab3.SNS_TableMiddle;
0021 "HMI_Transfer".Status.SNS.TAB3.Low_level := "Transfer_DB".Tab3.SNS_TableDown;
0022
0023 "HMI_Transfer".Status.SNS.TAB3.Presence1 := "Transfer_DB".Tab3.SNS_Presence1;
0024 "HMI_Transfer".Status.SNS.TAB3.Presence2 := "Transfer_DB".Tab3.SNS_Presence2;
0025
0026 // TAB4
0027 "HMI_Transfer".Status.SNS.TAB4.High_level := "Transfer_DB".Tab4.SNS_TableTop;
0028 "HMI_Transfer".Status.SNS.TAB4.Middle_level := "Transfer_DB".Tab4.SNS_TableMiddle;
0029 "HMI_Transfer".Status.SNS.TAB4.Low_level := "Transfer_DB".Tab4.SNS_TableDown;
0030
0031 "HMI_Transfer".Status.SNS.TAB4.Presence1 := "Transfer_DB".Tab4.SNS_Presence1;
0032 "HMI_Transfer".Status.SNS.TAB4.Presence2 := "Transfer_DB".Tab4.SNS_Presence2;
0033
0034 // TAB5
0035 "HMI_Transfer".Status.SNS.TAB5.High_level := "Transfer_DB".Tab5.SNS_TableTop;
0036 "HMI_Transfer".Status.SNS.TAB5.Middle_level := "Transfer_DB".Tab5.SNS_TableMiddle;
0037 "HMI_Transfer".Status.SNS.TAB5.Low_level := "Transfer_DB".Tab5.SNS_TableDown;
0038
0039 "HMI_Transfer".Status.SNS.TAB5.Presence1 := "Transfer_DB".Tab5.SNS_Presence1;
0040 "HMI_Transfer".Status.SNS.TAB5.Presence2 := "Transfer_DB".Tab5.SNS_Presence2;
```

Network 2: Status declaration

```
0001 // TAB1
0002 "HMI_Transfer".Status.STS.TAB1.Discharge := "Transfer_DB".Tab1.FLAG_Discharge;
0003 "HMI_Transfer".Status.STS.TAB1.Waiting := "Transfer_DB".Tab1.FLAG_Waiting;
0004 "HMI_Transfer".Status.STS.TAB1.Fault := "Transfer_DB".Tab1.FLAG_Alarm;
0005
0006 // TAB2
0007 "HMI_Transfer".Status.STS.TAB2.Discharge := "Transfer_DB".Tab2.FLAG_Discharge;
0008 "HMI_Transfer".Status.STS.TAB2.Feed_TAB1 := "Transfer_DB".Tab2.FLAG_PassingNext;
0009 "HMI_Transfer".Status.STS.TAB2.Waiting := "Transfer_DB".Tab2.FLAG_Waiting;
0010 "HMI_Transfer".Status.STS.TAB2.Fault := "Transfer_DB".Tab2.FLAG_Alarm;
0011
0012 // TAB3
0013 "HMI_Transfer".Status.STS.TAB3.Feed := "Transfer_DB".Tab3.FLAG_Feeding;
0014 "HMI_Transfer".Status.STS.TAB3.Feed_TAB5 := "Transfer_DB".Tab3.FLAG_PassingNext;
0015 "HMI_Transfer".Status.STS.TAB3.Waiting := "Transfer_DB".Tab3.FLAG_Waiting;
0016 "HMI_Transfer".Status.STS.TAB3.Fault := "Transfer_DB".Tab3.FLAG_Alarm;
0017
0018 // TAB4
```

Totally Integrated Automation Portal		
<pre>0019 "HMI_Transfer".Status.STS.TAB4.Feed := "Transfer_DB".Tab4.FLAG_Feeding; 0020 "HMI_Transfer".Status.STS.TAB4.Feed_TAB2 := "Transfer_DB".Tab4.FLAG_PassingNext; 0021 "HMI_Transfer".Status.STS.TAB4.Waiting := "Transfer_DB".Tab4.FLAG_Waiting; 0022 "HMI_Transfer".Status.STS.TAB4.Fault := "Transfer_DB".Tab4.FLAG_Alarm; 0023 0024 // TAB5 0025 "HMI_Transfer".Status.STS.TAB5.Feed := "Transfer_DB".Tab5.FLAG_Feeding; 0026 "HMI_Transfer".Status.STS.TAB5.Feed_TAB4 := "Transfer_DB".Tab5.FLAG_PassingNext; 0027 "HMI_Transfer".Status.STS.TAB5.Waiting := "Transfer_DB".Tab5.FLAG_Waiting; 0028 "HMI_Transfer".Status.STS.TAB5.Fault := "Transfer_DB".Tab5.FLAG_Alarm; 0029 0030 // Chain 0031 "HMI_Transfer".Status.STS.Chain_Move := 0032 "Transfer_DB".Tab2.FLAG_PassingNext OR 0033 "Transfer_DB".Tab3.FLAG_PassingNext OR 0034 "Transfer_DB".Tab4.FLAG_PassingNext OR 0035 "Transfer_DB".Tab5.FLAG_PassingNext; 0036</pre> Network 3: Alarms declaration <pre>0001 // TAB1 Alarms 0002 "HMI_Transfer".Alarms.AlarmsWORD1.%X0 := "Transfer_DB".Tab1.ALM_OverlapSNS; 0003 "HMI_Transfer".Alarms.AlarmsWORD1.%X1 := "Transfer_DB".Tab1.ALM_OverlapSTS; 0004 "HMI_Transfer".Alarms.AlarmsWORD1.%X2 := "Transfer_DB".Tab1.ALM_Presence; 0005 "HMI_Transfer".Alarms.AlarmsWORD1.%X3 := "Transfer_DB".Tab1.ALM_TermicShoutdownElevation; 0006 "HMI_Transfer".Alarms.AlarmsWORD1.%X4 := "Transfer_DB".Tab1.ALM_TermicShoutdownTransport; 0007 "HMI_Transfer".Alarms.AlarmsWORD1.%X5 := "Transfer_DB".Tab1.ALM_TimeOutBackard; 0008 "HMI_Transfer".Alarms.AlarmsWORD1.%X6 := "Transfer_DB".Tab1.ALM_TimeOutChangeTableLevel; 0009 "HMI_Transfer".Alarms.AlarmsWORD1.%X7 := "Transfer_DB".Tab1.ALM_TimeOutFordward; 0010 0011 // TAB2 Alarms 0012 "HMI_Transfer".Alarms.AlarmsWORD1.%X8 := "Transfer_DB".Tab2.ALM_OverlapSNS; 0013 "HMI_Transfer".Alarms.AlarmsWORD1.%X9 := "Transfer_DB".Tab2.ALM_OverlapSTS; 0014 "HMI_Transfer".Alarms.AlarmsWORD1.%X10 := "Transfer_DB".Tab2.ALM_Presence; 0015 "HMI_Transfer".Alarms.AlarmsWORD1.%X11 := "Transfer_DB".Tab2.ALM_TermicShoutdownElevation; 0016 "HMI_Transfer".Alarms.AlarmsWORD1.%X12 := "Transfer_DB".Tab2.ALM_TermicShoutdownTransport; 0017 "HMI_Transfer".Alarms.AlarmsWORD1.%X13 := "Transfer_DB".Tab2.ALM_TimeOutBackard; 0018 "HMI_Transfer".Alarms.AlarmsWORD1.%X14 := "Transfer_DB".Tab2.ALM_TimeOutChangeTableLevel; 0019 "HMI_Transfer".Alarms.AlarmsWORD1.%X15 := "Transfer_DB".Tab2.ALM_TimeOutFordward; 0020 0021 // TAB3 Alarms 0022 "HMI_Transfer".Alarms.AlarmsWORD2.%X0 := "Transfer_DB".Tab3.ALM_OverlapSNS; 0023 "HMI_Transfer".Alarms.AlarmsWORD2.%X1 := "Transfer_DB".Tab3.ALM_OverlapSTS; 0024 "HMI_Transfer".Alarms.AlarmsWORD2.%X2 := "Transfer_DB".Tab3.ALM_Presence; 0025 "HMI_Transfer".Alarms.AlarmsWORD2.%X3 := "Transfer_DB".Tab3.ALM_TermicShoutdownElevation; 0026 "HMI_Transfer".Alarms.AlarmsWORD2.%X4 := "Transfer_DB".Tab3.ALM_TermicShoutdownTransport; 0027 "HMI_Transfer".Alarms.AlarmsWORD2.%X5 := "Transfer_DB".Tab3.ALM_TimeOutBackard; 0028 "HMI_Transfer".Alarms.AlarmsWORD2.%X6 := "Transfer_DB".Tab3.ALM_TimeOutChangeTableLevel; 0029 "HMI_Transfer".Alarms.AlarmsWORD2.%X7 := "Transfer_DB".Tab3.ALM_TimeOutFordward; 0030 0031 // TAB4 Alarms 0032 "HMI_Transfer".Alarms.AlarmsWORD2.%X8 := "Transfer_DB".Tab4.ALM_OverlapSNS; 0033 "HMI_Transfer".Alarms.AlarmsWORD2.%X9 := "Transfer_DB".Tab4.ALM_OverlapSTS; 0034 "HMI_Transfer".Alarms.AlarmsWORD2.%X10 := "Transfer_DB".Tab4.ALM_Presence; 0035 "HMI_Transfer".Alarms.AlarmsWORD2.%X11 := "Transfer_DB".Tab4.ALM_TermicShoutdownElevation; 0036 "HMI_Transfer".Alarms.AlarmsWORD2.%X12 := "Transfer_DB".Tab4.ALM_TermicShoutdownTransport; 0037 "HMI_Transfer".Alarms.AlarmsWORD2.%X13 := "Transfer_DB".Tab4.ALM_TimeOutBackard; 0038 "HMI_Transfer".Alarms.AlarmsWORD2.%X14 := "Transfer_DB".Tab4.ALM_TimeOutChangeTableLevel; 0039 "HMI_Transfer".Alarms.AlarmsWORD2.%X15 := "Transfer_DB".Tab4.ALM_TimeOutFordward; 0040 0041 // TAB5 Alarms 0042 "HMI_Transfer".Alarms.AlarmsWORD3.%X0 := "Transfer_DB".Tab5.ALM_OverlapSNS; 0043 "HMI_Transfer".Alarms.AlarmsWORD3.%X1 := "Transfer_DB".Tab5.ALM_OverlapSTS; 0044 "HMI_Transfer".Alarms.AlarmsWORD3.%X2 := "Transfer_DB".Tab5.ALM_Presence; 0045 "HMI_Transfer".Alarms.AlarmsWORD3.%X3 := "Transfer_DB".Tab5.ALM_TermicShoutdownElevation; 0046 "HMI_Transfer".Alarms.AlarmsWORD3.%X4 := "Transfer_DB".Tab5.ALM_TermicShoutdownTransport; 0047 "HMI_Transfer".Alarms.AlarmsWORD3.%X5 := "Transfer_DB".Tab5.ALM_TimeOutBackard; 0048 "HMI_Transfer".Alarms.AlarmsWORD3.%X6 := "Transfer_DB".Tab5.ALM_TimeOutChangeTableLevel; 0049 "HMI_Transfer".Alarms.AlarmsWORD3.%X7 := "Transfer_DB".Tab5.ALM_TimeOutFordward; 0050 0051 // Chain Transfer Alarms 0052 "HMI_Transfer".Alarms.AlarmsWORD3.%X8 := "Transfer_DB".ChainTransfer.ALM_Motor; 0053 "HMI_Transfer".Alarms.AlarmsWORD3.%X9 := "Transfer_DB".ChainTransfer.ALM_TimeOutTAB2; 0054 "HMI_Transfer".Alarms.AlarmsWORD3.%X10 := "Transfer_DB".ChainTransfer.ALM_TimeOutTAB3; 0055 "HMI_Transfer".Alarms.AlarmsWORD3.%X11 := "Transfer_DB".ChainTransfer.ALM_TimeOutTAB4; 0056 "HMI_Transfer".Alarms.AlarmsWORD3.%X12 := "Transfer_DB".ChainTransfer.ALM_TimeOutTAB5; 0057 0058 // Safety 0059 "HMI_Transfer".Alarms.AlarmsWORD3.%X13 := "Transfer_DB".Safety.Barrier1; 0060 "HMI_Transfer".Alarms.AlarmsWORD3.%X14 := "Transfer_DB".Safety.Barrier2; 0061 "HMI_Transfer".Alarms.AlarmsWORD3.%X15 := "Transfer_DB".Safety.Door1; 0062 "HMI_Transfer".Alarms.AlarmsWORD4.%X0 := "Transfer_DB".Safety.Door2; 0063 "HMI_Transfer".Alarms.AlarmsWORD4.%X1 := "Transfer_DB".Safety.Emergency; 0064 0065</pre>		

Totally Integrated Automation Portal		
Network 4: Comands declaration <pre>0001 // Deposits 0002 "Transfer_DB".Comands.Deposit1On := "HMI_Transfer".Comands.Deposit1On; 0003 "Transfer_DB".Comands.Deposit2On := "HMI_Transfer".Comands.Deposit2On; 0004 "Transfer_DB".Comands.Deposit3On := "HMI_Transfer".Comands.Deposit3On; 0005 "Transfer_DB".ChainTransfer.FLAG_AlterneDepo1Depo2 := "HMI_Transfer".Comands.AlterneD1D2; 0006 0007 // Manual Comands 0008 IF "Transfer_DB".Comands.ManualQ1 = FALSE THEN 0009 "HMI_Transfer".Status.STS.Manual_Moves := 0; 0010 END_IF; 0011 0012 "Transfer_DB".ChainTransfer.CMD_ChainBackward := FALSE; 0013 "Transfer_DB".ChainTransfer.CMD_ChainFordward := FALSE; 0014 0015 "Transfer_DB".Tab1.CMD_Backward := FALSE; 0016 "Transfer_DB".Tab1.CMD_Fordward := FALSE; 0017 "Transfer_DB".Tab1.CMD_ChangeLevel := FALSE; 0018 0019 "Transfer_DB".Tab2.CMD_Backward := FALSE; 0020 "Transfer_DB".Tab2.CMD_Fordward := FALSE; 0021 "Transfer_DB".Tab2.CMD_ChangeLevel := FALSE; 0022 0023 "Transfer_DB".Tab3.CMD_Backward := FALSE; 0024 "Transfer_DB".Tab3.CMD_Fordward := FALSE; 0025 "Transfer_DB".Tab3.CMD_ChangeLevel := FALSE; 0026 0027 "Transfer_DB".Tab4.CMD_Backward := FALSE; 0028 "Transfer_DB".Tab4.CMD_Fordward := FALSE; 0029 "Transfer_DB".Tab4.CMD_ChangeLevel := FALSE; 0030 0031 "Transfer_DB".Tab5.CMD_Backward := FALSE; 0032 "Transfer_DB".Tab5.CMD_Fordward := FALSE; 0033 "Transfer_DB".Tab5.CMD_ChangeLevel := FALSE; 0034 0035 0036 CASE "HMI_Transfer".Status.STS.Manual_Moves OF 0037 1: 0038 "Transfer_DB".ChainTransfer.CMD_ChainBackward := TRUE; 0039 2: 0040 "Transfer_DB".ChainTransfer.CMD_ChainFordward := TRUE; 0041 3: 0042 "Transfer_DB".Tab1.CMD_Backward := TRUE; 0043 4: 0044 "Transfer_DB".Tab1.CMD_Fordward := TRUE; 0045 5: 0046 "Transfer_DB".Tab1.CMD_ChangeLevel := TRUE; 0047 6: 0048 "Transfer_DB".Tab2.CMD_Backward := TRUE; 0049 7: 0050 "Transfer_DB".Tab2.CMD_Fordward := TRUE; 0051 8: 0052 "Transfer_DB".Tab2.CMD_ChangeLevel := TRUE; 0053 9: 0054 "Transfer_DB".Tab3.CMD_Backward := TRUE; 0055 10: 0056 "Transfer_DB".Tab3.CMD_Fordward := TRUE; 0057 11: 0058 "Transfer_DB".Tab3.CMD_ChangeLevel := TRUE; 0059 12: 0060 "Transfer_DB".Tab4.CMD_Backward := TRUE; 0061 13: 0062 "Transfer_DB".Tab4.CMD_Fordward := TRUE; 0063 14: 0064 "Transfer_DB".Tab4.CMD_ChangeLevel := TRUE; 0065 15: 0066 "Transfer_DB".Tab5.CMD_Backward := TRUE; 0067 16: 0068 "Transfer_DB".Tab5.CMD_Fordward := TRUE; 0069 17: 0070 "Transfer_DB".Tab5.CMD_ChangeLevel := TRUE; 0071 END_CASE;</pre>		