

LPG Vending Machines API Documentation

Version 1.0.1

Prepared By

Manivannan

Table of Contents

- LPG Vending Machines API Documentation.....3
 - Overview.....3
 - Base URL.....3
 - Authentication.....3
 - Endpoint.....3
 - Description.....3
 - Request.....3
 - Response.....3
 - Get Machines.....3
 - Endpoint.....3
 - Description.....3
 - Request.....4
 - Response.....4
 - Check Machine Subscription.....4
 - Endpoint.....4
 - Description.....4
 - Request.....4
 - Response.....4
 - Notes.....4

LPG Vending Machines API Documentation

Overview

This API provides functionalities for managing and interacting with LPG vending machines. It supports user authentication, fetching machine details, and checking machine subscriptions.

Base URL

All API endpoints use the following base URL:

`http://demo.lifotechnologies.com/`

Authentication

Endpoint

POST `{{APIURL}}api/token/`

Description

Authenticates a user and generates an access token.

Request

- **Headers:** None
- **Body (form-data):**
 - `username:` (string) User's username (e.g., manivannan)
 - `password:` (string) User's password (e.g., lifo@123)

Response

Returns an access token for authenticated requests.

Get Machines

Endpoint

GET `{{APIURL}}api/machines/1`

Description

Fetches the details of a specific LPG vending machine.

Request

- **Headers:**
 - Authorization: Bearer token (e.g., Bearer {{BEARER_TOKEN}})
- **Parameters:** None

Response

Returns the details of the machine with ID 1.

Check Machine Subscription

Endpoint

POST {{APIURL}}api/check-subscription/

Description

Checks whether a specific machine has an active subscription.

Request

- **Headers:**
 - Authorization: Bearer token (e.g., Bearer {{BEARER_TOKEN}})
- **Body (raw, JSON):**

```
{
  "machine_id": "123456890"
}
```

Response

Returns the subscription status of the machine.

Notes

1. Replace {{APIURL}} with **http://demo.lifotechnologies.com/**.
2. Replace {{BEARER_TOKEN}} with the token obtained from the authentication endpoint.