




1. Downloading AssmSoft and Software from google classroom:




2. Extraction of software.zip




3. Extraction of assmsoft.zip




4. Install DosBox




5. Making of Assembly folder:




6. Pasting all AssmSoft files in assembly:




7. Installing .asmfolder:




8. Move asm files to assembly :




9. Run dosbox:




10. Mount x:




11. Go to x drive:



12. Run NASM:



13. Check if NASM run without error:



The screenshot shows a DOSBox 0.74-3 terminal window. A blue welcome message box is displayed at the top, providing instructions for new users. Below the box, the user enters the command 'SET BLASTER=A220 I7 D1 H5 T6' at the Z:\ prompt. Then, they enter 'mount x d:/assembly' at the Z:\ prompt, and the system responds 'Drive X is mounted as local directory d:/assembly'. Finally, they enter 'x:\nas' at the X:\ prompt, and the system responds 'X:\nas'. The user then enters 'nasm c01_01.asm' at the X:\ prompt, and the system responds 'nasm: fatal: unable to open input file 'c01_01.asm''. The user then enters 'x:\nas' at the X:\ prompt, and the system responds 'X:\nas'.

```
Box Status Window
on 0.74-3
002-2019
ng prim
device:

DOSBox 0.74-3, ...
Welcome to DOSBox v0.74-3
For a short introduction for new users type: INTRO
For supported shell commands type: HELP
To adjust the emulated CPU speed, use ctrl-F11 and ctrl-F12.
To activate the keymapper ctrl-F1.
For more information read the README file in the DOSBox directory.
HAVE FUN!
The DOSBox Team http://www.dosbox.com


Z:\>SET BLASTER=A220 I7 D1 H5 T6

Z:\>mount x d:/assembly
Drive X is mounted as local directory d:/assembly\

Z:\>x:

X:\>nasm c01_01.asm
nasm: fatal: unable to open input file 'c01_01.asm'
X:\>nasm c01-01.asm
X:\>_
```

14. Making output file :



The screenshot shows a DOSBox 0.74-3 terminal window. The user enters 'SET BLASTER=A220 I7 D1 H5 T6' at the Z:\ prompt. Then, they enter 'x:' at the Z:\ prompt, and the system responds 'Drive X does not exist! You must mount it first. Type intro or intro mount for more information.'. The user then enters 'mount x d:/assembly' at the Z:\ prompt, and the system responds 'Drive X is mounted as local directory d:/assembly\'. The user then enters 'mount x d:/assembly' at the Z:\ prompt, and the system responds 'Drive X already mounted with local directory d:/assembly\'. The user then enters 'mount x d:/assembly' at the Z:\ prompt, and the system responds 'Drive X already mounted with local directory d:/assembly\'. The user then enters 'x:' at the Z:\ prompt, and the system responds 'X:\'. The user then enters 'nasm c01-01.asm' at the X:\ prompt, and the system responds 'X:\'. The user then enters 'nasm c01-01.asm -o c01-01.com' at the X:\ prompt, and the system responds 'X:\'. The user then enters 'x:' at the X:\ prompt, and the system responds 'X:\'.

```
DOSBox 0.74-3, ...
The DOSBox Team http://www.dosbox.com

Z:\>SET BLASTER=A220 I7 D1 H5 T6

Z:\>x:
Drive X does not exist!
You must mount it first. Type intro or intro mount for more information.

Z:\>mount x d:/assembly
Drive X is mounted as local directory d:/assembly\


Z:\>mount x d:/assembly
Drive X already mounted with local directory d:/assembly\

Z:\>mount x d:/assembly
Drive X already mounted with local directory d:/assembly\


Z:\>x:

X:\>nasm c01-01.asm
X:\>nasm c01-01.asm -o c01-01.com
X:\>x:
X:\>
```


15. Check output file in Assembly folder :




16. Making .lst file:




17. .lst file in assembly folder :



18. Download notepad++:




19. Lst file in notebook++:



```
1 1 [org 0x0100]
2 2 ; start of code
3 3
4 4
5 5 00000005 B0500 mov ax, 5 ; move the constant 5 into register ax
6 6 0000000B B0A00 mov bx, 10
7 7
8 8
9 9 00000006 01D8 add ax, bx ; add value of bx into the value of ax
10 10
11 11 00000008 B0F00 mov bx, 15 ; add constant 15 into the value of bx
12 12 0000000B 01D8 add ax, bx
13 13
14 14 0000000D B004C mov ax, 0x4C00 ; exit ..
15 15 00000010 CD21 int 0x21 ; .. is what the OS should do for me
16 16
17 17
18 18
19 19
20 20
21 21
22 22
23 23
24 24 ; watch the listing carefully
25 25
```

20. afd interface of .com file:



```
DOSBox 0.74-3,...
AX:0000 SI:0000 CS:19F5 IP:0100 Stack:0000 Flags:7202
BX:0000 DI:0000 DS:19F5 +2:200D
CX:0012 BP:0000 ES:19F5 HS:19F5 +4:9FFF 0F DF IF SF ZF AF PF CF
DX:0000 SP:FFFF SS:19F5 FS:19F5 +6:D400 00 01 00 00 00 00

CMD >
0100 B0500 MOV AX,0005
0103 B0A00 MOV BX,000B
0106 01D8 ADD AX,BX
0109 B0F00 MOV BX,000F
010B 01D8 ADD AX,BX
010D B004C MOV AX,4C00
0110 CD21 INT 21
0112 EB04 JMP 0110
DS:0000 00 01 2 3 4 5 6 7
DS:0000 CD 20 FF 9F 00 EA F0 FE AD DE 1B 05 C5 06 00 00
DS:0010 18 01 10 01 18 01 32 01 01 01 01 00 02 FF FF FF
DS:0018 01 01 01 00 02 FF FF FF
DS:0020 FF FF FF FF FF FF FF FF
DS:0028 FF FF FF FF EB 19 C0 11
DS:0030 A2 01 14 00 10 00 F5 19 FF FF FF 00 00 00 00
DS:0040 05 00 00 00 00 00 00 00
DS:0048 00 00 00 00 00 00 00 00
```