

User Manual For BOM Creation Using Copy Paste function And Modification of BOM

Submitted to:



Bajaj Electricals Limited

Rustomjee Aspire, 7th Floor,
Bhanu Shankar Yagnik Marg,
Sion East,
Mumbai
Maharashtra – 400022, India

Submitted by:



Softcell Technologies Global Pvt. Ltd.

401, Mayfair Tower-1,
Wakdewadi, Shivajinagar,
Pune
Maharashtra – 411005, India.

Document History

Version	Date	Owner	Description
00	06-03-2024	Softcell Technologies Global Pvt. Ltd.	BOM Creation Using Copy & Paste Function And BOM Modification

Document Author

Mr. Bhagyawan Solanke	bsolanke@softcell.com
-----------------------	--

Approved & Reviewed By

Mr. Ravichandran M A	ravichandran@softcell.com
Mr. Suresh Vasu	sureshv@softcell.com
Ms. Bhagyashree Kulkarni	bkulkarni@softcell.com

Contents

INTRODUCTION	4
Windchill URL and Navigation.....	5
Product Code Creation in Windchill	7
Structure Building using Copy paste.....	8
Modification of BOM Structure.....	11
Remove unnecessary parts	11
Addition of parts in structure.....	11

INTRODUCTION


This document is prepared to show the windchill copy paste functionality to built the EBOM structure and by utilizing the basic functionality of windchill to modify the Bill Of Material by adding and removing parts .

Windchill URL and Navigation

- Enter below URL in Web Browser and enter username and credential.


Windchill URL: - <http://belazplm-uat-ap.bel.com/Windchill/app>

Windchill Home Page will Open




- Navigate to Parts Library


Click on Navigate - Browse < Go to Library< CP & MR WTParts



- Click on Folders



- Create new Part




Product Code Creation in Windchill

Click on New part < Select “BEL_CP “ type, Fill At least mandatory attribute values

Then Click on Finish


The screenshot shows the 'New Part' wizard in Windchill, specifically the 'Set Attributes' step. The browser window title is 'New Part - Google Chrome' and the URL is 'belazplm-uat-ap.bel.com/Windchill/ptc1/part/createPartWizard?revisionMode=crea...'. The page title is 'New Part'. The 'Set Attributes' section includes a dropdown for 'CP & MR WTParts' set to 'BEL_CP', and a checkbox for 'as End Item' set to 'No'. The 'Part Attributes' section includes a 'Part Code' field with 'B0340', a 'Number' field with '(Generated)', a 'Name' field with 'Test BOM Copy Paste Function', an 'Assembly Type' dropdown set to 'Component', a 'Make' dropdown, an 'Untraced' dropdown, a 'Unit' dropdown set to 'each', and checkboxes for 'ering' and 'Item Manufacturing' both set to 'No'. The 'Cycle' and 'Plate' fields are both set to '(Generated)'. The 'Location' section has two radio buttons: 'Autoselect Folder (/CP & MR WTParts)' and 'Select Folder (/CP & MR WTParts)', with the latter selected. The 'Description' field contains 'test object'. The 'Parent' field is set to 'DAB'. At the bottom, there is a note '* Indicates required fields.' and four buttons: 'Back', 'Next', 'Finish', and 'Cancel'. The 'Finish' button is highlighted.

Part automatically resides in folder of related base code.




Structure Building using Copy paste


- We are going to create structure for below created part which has no parts in structure



- Go to Structure of other Part from where we need to copy structure
- Select the parts need to paste in new Part and copy



- Go to Part to which structure has to be create.
- Click on Paste icon.



- Below Window Opens, Provide valid inputs and click OK

The screenshot shows the Windchill 'Usage Attributes' dialog for the item 'BEL_CP - B0340AX3465, Test BOM Copy Paste Function, 00.1 (Design)'. The dialog is open over the 'Details' tab of the item's page. The 'Usage Attributes' section contains the following fields:

- Find Number:** (empty text box)
- Line Number:** (empty text box)
- *Quantity:** 1
- Reference Designator:** (empty text box)
- *Trace Code:** Untraced (dropdown menu)
- *Unit:** each (dropdown menu)
- Usage Soft Attributes:**
 - *PIM/U Type:** (dropdown menu with a red warning icon)

At the bottom right of the dialog are 'OK' and 'Cancel' buttons. A note at the bottom left states '*Indicates required field'.

- User can See the Pasted Structure in below image

The screenshot shows the Windchill 'Structure' tab for the item 'BEL_CP - B0340AX3465, Test BOM Copy Paste Function, 00.1 (Design)'. The table displays the BOM structure with the following columns: Object Type, Line Number, Name, Quantity, and Unit.


Object Type	Line Number	Name	Quantity	Unit
BEL_CP	B0340AX3465	Test BOM Copy Paste Function		
BEL_CP	A0050AX3464	Test BOM Excel	2	each
BEL_CP	A0010A00418	750W_motor_blue_leaf	1	each
BEL_CP	A0020A00039	MOTOR ASSLY 500W	1	each
BEL_CP	10 A0050A00369	CONTROL PANEL ASSEMBLY	2	each
BEL_CP	20 A0050AX0367	TANK 4SLASSEMBLY	5	each
BEL_CP	30 A0050AX0176	BACK ASSEMBLY	1	each
BEL_CP	40 A0050AX0168	SIDE ASSEMBLY	1	each
BEL_CP	50 A0050AX0164	TOP ASSEMBLY	3	each
BEL_CP	60 A0050A00150	MOTOR & FAN ASSEMBLY	1	each
BEL_CP	70 A0050AX0149	CONTROL PANEL ASSEMBLY	1	each
BEL_CP	80 A0050AX0098	55L- TANK & WLI ASSEMBLY	1	each

The table shows 12 objects in total. The right side of the interface displays various tabs like 'Attributes', 'Classification', 'Visualization', 'Uses', 'Occurrences', 'Effectivity', and 'Supersedes'.

Modification of BOM Structure

Remove unnecessary parts


Select not required parts < Click on remove



Addition of parts in structure

- User can copy and paste from another code structure
- Addition of Parts using search

User can search number by clicking  or at the end search number



Copy Paste Function, 00.2 (Design) In Work

Where Used AML/AVL FG Code Vendor Details

Clipboard Viewing New/Add To Filter Tools

Paste Copy Show Hide Views New Add to Current Filter Path Filter Edit Filter Saved Filters Enter name or number Compare Open in

Design Working

Name	Quantity	Unit	Attributes	Classification	Visualization	Uses	Occurrences	Effectivity	Supersedes
Test BOM Copy Paste Function									
Test BOM Excel	1	ea							
750W_motor_blue_Leaf	1	ea							
MOTOR ASSLY 500W	1	ea							
CONTROL PANEL ASSEMBLY	2	ea							
TANK 45L ASSEMBLY	5	ea							
BACK ASSEMBLY	1	ea							
SIDE ASSEMBLY	1	ea							
TOP ASSEMBLY	3	ea							
MOTOR & FAN ASSEMBLY	1	ea							
CONTROL PANEL ASSEMBLY	1	ea							
55L- TANK & WLI ASSEMBLY	1	ea							

Part Gro...	Number	Quantity	Unit	Name	Version	Line h
	A0010			Finish Motor Body (...)		
	A0010A00010			Attribute Test		
	A0010A00090			base_unit_elegance		
	A0010A00418			750W_motor_blue_I...		
	A0010A00433			1000W_motor_blue...		
	A0010A00442			Motor Assembly Ad...		
	A0010A01366			mg_t1_1000_ay_jmg		
	A0010AX0444			Motor assembly for ...		
	A0010C00001			Test 1		
	A0020			Motor Body (MB)		
	A0020A00039			MOTOR ASSLY 500W		
	A00			Enter Name		

More search options Create this part

Displaying 1 - 10 of 10

By scrolling user can select required part and add in structure.

Attributes	Classification	Visualization	Uses	Occurrences	Effectivity	Supersedes
Part Gro...	Number	Quantity	Unit	Name	Version	Line h
	A0030A03157	2122-02/0009 STAT.		MOTOR ASSLY ...	00.1 (Design)	
	A0030A03251	PD 2568 STATOR A.		MOTOR & FAN ...	00.1 (Design)	60
	A0040	Assembled Bottom		CONTROL PAN...	00.1 (Design)	10
	A0040AX1440	TANK ASSEMBLY-3.		55L- TANK & W...	00.1 (Design)	80
	A0040AX1441	CL-PC-36&26-A-Y...		CONTROL PAN...	00.1 (Design)	70
	A0040AX1444	FRONT COVER AS.		TOP ASSEMBLY	00.1 (Design)	50
	A0040AX1445	MOTOR MOUNTIN...		SIDE ASSEMBLY	00.1 (Design)	40
	A0040AX1446	TOP COVER ASSY		BACK ASSEMBLY	00.1 (Design)	30
	A0040AX1447	BACK COVER ASS...		TANK 45L ASSE...	00.1 (Design)	20
	A0040AX1448	SIDE COVER ASSE...				
	A0040AX1449					
	A00			Enter Name		

More search options Create this part

Displaying 1 - 10 of 10