

INDIAN SPRINGS

Creech Air Force Base

AI_ATC VoiceAttack Command Reference

Complete Voice Command Reference

AI_ATC Version 2.9.27

VoiceAttack Profile Version 1.00

00 HOW TO USE THIS REFERENCE

PROFILE INITIALIZATION

When first loading the VoiceAttack profile, say “Set Airbase to Indian Springs” and then “Set Callsign Dodge Two One” before using any ATC command. Repeat these setup commands whenever you change the active airbase or callsign.

COMMAND NOTATION

NOTATION	MEANING
<Callsign>	Selected callsign, such as Dodge Two One
<Runway>	Valid Creech runway: 08, 13, 26 or 31
<Waypoint>	Valid navpoint for the relevant Nellis Control service
<Altitude>	Spoken altitude or flight level
<ATIS Code>	Information Alpha through Zulu
[Optional]	Word or phrase may be omitted
A / B	Either option may be spoken

Speak the controller name, callsign, and command as one continuous phrase unless the command is listed as callsign-only. Nellis Control provides both departure and approach radar services for Indian Springs.

01 CLEARANCE DELIVERY

UHF 372.200 | VHF 118.300

STANDARD SPOKEN FORMAT

Indian Springs Clearance, <Callsign>, clearance on request, <Clearance>

VFR CLEARANCE

SPOKEN OPTION	SUPPORTED ROUTING
VFR	Gate One - FLUSH - JAYSN - STRYK; maintain 7,000 ft as assigned

VFR-ONLY OPERATIONS

Indian Springs / Creech AFB is configured as a VFR-only field. Do not request an IFR departure from Clearance Delivery. Use the VFR clearance option shown above, then contact Nellis Control after departure as directed.

SQUAWK COMMANDS

PURPOSE	VOICEATTACK WORDING
Specific code	Squawk <code>
Sequential code	Squawk 1001 / 2001 / 3001 / 4001 / 5001 / 6001 / 7001 sequential

EXAMPLE

Indian Springs Clearance, Dodge Two One, clearance on request, VFR

02 GROUND CONTROL

UHF 275.800 | VHF 118.300

STANDARD SPOKEN FORMAT
Indian Springs Ground, <Callsign>, <Command>

GROUND COMMANDS

PURPOSE	RECOGNIZED COMMAND
Engine start	Request engine start
Taxi	Request taxi / request taxi to runway
Taxi with ATIS	Request taxi with [information] <ATIS Code>
Holding short	Holding short [runway] <Runway>
Parking	Request taxi to park / parking
Hover check	Request hover check

VALID RUNWAYS

RUNWAY	SPOKEN FORM
08	Zero Eight
13	One Three
26	Two Six
31	Three One

EXAMPLE
Indian Springs Ground, Dodge Two One, request taxi with information Alpha

03 TOWER

UHF 360.600 | VHF 118.300

STANDARD SPOKEN FORMAT

Indian Springs Tower, <Callsign>, <Command>

DEPARTURE COMMANDS

PURPOSE	RECOGNIZED COMMAND
Ready	Request takeoff / ready for takeoff / ready for departure / number one
Holding short	Holding short [runway] Zero Eight / One Three / Two Six / Three One
Climb	Request [unrestricted / quick] climb to / through <Altitude>
Helicopter	Request hover check / request takeoff from parking

PATTERN AND LANDING

PURPOSE	RECOGNIZED COMMAND
Initial / overhead	Initial / at initial / request the overhead / request initial / ready overhead
Special pattern	Request high tactical initial / overhead; request SFO; high key; low key
Base call	Left / right base, <gear report>, <landing intention>
Mileage call	Three / five miles, <gear report>, <landing intention>
Straight-in	Request straight in / straight-in landing
Closed traffic	Request closed / closed traffic
Other	Extending downwind / missed approach / runway in sight / traffic in sight / no joy / say winds

EXAMPLE

Indian Springs Tower, Dodge Two One, left base, gear down, full stop

04 NELLIS CONTROL - DEPARTURE

UHF 254.400 | VHF 119.350

STANDARD SPOKEN FORMAT
Nellis Control, <Callsign>, <Command>

DEPARTURE SERVICE

PURPOSE	RECOGNIZED COMMAND
Initial contact	Checking in
Altitude report	Airborne passing / passing <Altitude> thousand
Waypoint report	Is / passing / reporting <Waypoint>
Vector request	Request vector / request vectors / request a vector [to / for] <Waypoint>
Approach request	Request approach
Radar identification	Flash

DEPARTURE VECTOR FORMAT
Nellis Control, <Callsign>, request vector to <Waypoint>

VALID DEPARTURE NAVPOINTS

GROUP	VALID NAVPOINTS
IFR departure fixes	ESSAA; JAYSN; LEAHI; Tonopah TACAN; STOFF
VFR departure route	Gate One; FLUSH; JAYSN; STRYK
Runway / local points	Runway 08 FAF; Runway 13 FAF; Runway 26 FAF; Runway 31 FAF

EXAMPLE
Nellis Control, Dodge Two One, request vector to JAYSN

05 NELLIS CONTROL - APPROACH

UHF 254.400 | VHF 119.350 SFA UHF 343.725 | VHF 124.950

STANDARD SPOKEN FORMAT

Nellis Control, <Callsign>, <Command>

APPROACH AND RECOVERY SERVICE

SERVICE	RECOGNIZED REQUEST
Initial / status	Checking in; checking in VFR / IFR; cancel IFR; request IFR pickup
High TACAN	Request high TACAN / high TACAN approach
TACAN	Request TACAN / TACAN approach / TACAN final
ILS / LOC	Request ILS / ILS approach / ILS final
RNAV	Request RNAV / RNAV approach
PAR / GCA	Request PAR approach / request GCA / request a GCA pickup
Recovery	Missed approach; breaking out; request back to radar; runway in sight
Closed traffic	Request closed / closed traffic

APPROACH VECTOR FORMAT

Nellis Control, <Callsign>, request vector to <Waypoint>

VALID APPROACH NAVPOINTS

PROCEDURE / ROUTE	VALID NAVPOINTS
High TACAN Runway 08	PIUTE
High TACAN Runway 26	17 DME
VFR / local recovery	Gate One; FLUSH; JAYSN; STRYK
Final approach points	Runway 08 FAF; Runway 13 FAF; Runway 26 FAF; Runway 31 FAF
Radar pattern	Downwind; Base

EXAMPLE

Nellis Control, Dodge Two One, request high TACAN Runway Zero Eight

06 RANGE CONTROL

BLACKJACK UHF 377.800 | VHF 125.300

STANDARD SPOKEN FORMAT
Blackjack, <Callsign>, <Command>

RANGE CONTROL COMMANDS

PURPOSE	VOICEATTACK WORDING
Initial contact	Checking in [at] <range gate / named point>
Check out	Checking out [at / from] <location>
Return to Creech	RTB for recovery at Creech / Indian Springs
Approach to Creech	RTB for approach to Creech / Indian Springs
Vector request	Request vector to <named range point>
Status / support	Words; say winds; pressure; request tanker when available

CREECH / INDIAN SPRINGS WORKFLOW

STAGE	AGENCY / ACTION
1	Advise Blackjack that you are checking out or RTB for Creech / Indian Springs.
2	Contact Nellis Control and request the required recovery or approach service.
3	Contact Indian Springs Tower when instructed or when established for the local procedure.

NAMED RANGE POINTS

COMMAND	ACCEPTED WORDING / OPTIONS
Range gates	Gate One; Gate Two; Gate Three; Gate Four
Named points	Point Alpha; Point Bravo; Point Charlie; Point Delta; Point Echo; Point Foxtrot; Point Golf; Point Hotel

EXAMPLE
Blackjack, Dodge Two One, RTB for approach to Indian Springs

07 CALLSIGN-ONLY COMMANDS

STANDARD SPOKEN FORMAT
<Callsign>, <Command>

FOLLOW-UP COMMANDS

PURPOSE	RECOGNIZED COMMAND
Pattern	Initial; ready overhead; high key; low key; extending downwind; request closed traffic
Landing	Left / right base, <gear report>, <landing intention>; three / five miles, <gear report>, <landing intention>
Radar	Missed approach; breaking out; request back to radar
Visual	Runway in sight; traffic in sight; no joy; say winds
Status	IFR / VFR
Report point	Reporting a valid Creech / Indian Springs or Nellis Control waypoint

EXAMPLE
Dodge Two One, runway in sight