

SILVERBOW

AI_ATC VoiceAttack Command Reference

Tonopah Test Range Airfield

AI_ATC Version 1.00

VoiceAttack Profile Version 1.00

00 HOW TO USE THIS REFERENCE

PROFILE INITIALIZATION

When first loading the VoiceAttack profile, say “Set Airbase to Silverbow” and then “Set Callsign Dodge Two One” before using any ATC command. Repeat these setup commands whenever you change the active airbase or callsign.

COMMAND NOTATION

NOTATION	MEANING
<Callsign>	Selected callsign, such as Dodge Two One
<Runway>	Valid Silverbow runway: 14 or 32
<Waypoint>	Valid navpoint for Nellis Control
<Altitude>	Spoken altitude or flight level
<ATIS Code>	Information Alpha through Zulu
[Optional]	Word or phrase may be omitted
A / B	Either option may be spoken

Speak the controller name, callsign, and command as one continuous phrase unless the command is listed as callsign-only. Nellis Control provides both departure and approach radar services for Silverbow.

01 CLEARANCE DELIVERY

UHF 233.950 | VHF 119.450

STANDARD SPOKEN FORMAT
Silverbow Clearance, <Callsign>, clearance on request, <Clearance>

VFR CLEARANCE

SPOKEN OPTION	SUPPORTED USE
VFR	Selects the local VFR departure profile
RUNWAY 14 DEPARTURE	Initial routing toward the Runway 14 final-approach-fix area
RUNWAY 32 DEPARTURE	Initial routing toward the Runway 32 final-approach-fix area

IFR DEPARTURES

SPOKEN DEPARTURE	INITIAL ROUTING / ALTITUDE
ESSA ONE	Direct ESSA; initial altitude 18,000 ft
JAYSN ONE	Direct JAYSN; initial altitude 18,000 ft
LEAHI ONE	Direct LEAHI; initial altitude 18,000 ft
RANGE TWO	Direct Tonopah TACAN; initial altitude 10,000 ft
SILVER ONE	Direct Tonopah TACAN; initial altitude 10,000 ft
STOFF TWO	Intercept the 137 radial toward STOFF; initial altitude 10,000 ft

SQUAWK COMMANDS

PURPOSE	VOICEATTACK WORDING
Specific code	Squawk <code>
Sequential code	Squawk 1001 / 2001 / 3001 / 4001 / 5001 / 6001 / 7001 sequential
EXAMPLE	
Silverbow Clearance, Dodge Two One, clearance on request, JAYSN One	

02 GROUND CONTROL

UHF 335.500 | VHF 127.250

STANDARD SPOKEN FORMAT
Silverbow Ground, <Callsign>, <Command>

GROUND COMMANDS

PURPOSE	RECOGNIZED COMMAND
Engine start	Request engine start
Taxi	Request taxi / request taxi to runway
Taxi with ATIS	Request taxi with [information] <ATIS Code>
Holding short	Holding short [runway] <Runway>
Parking	Request taxi to park / parking
Hover check	Request hover check

VALID RUNWAYS

RUNWAY	SPOKEN FORM
14	One Four
32	Three Two
EXAMPLE	
Silverbow Ground, Dodge Two One, request taxi with information Alpha	

03 TOWER

UHF 257.950 | VHF 124.750

STANDARD SPOKEN FORMAT
Silverbow Tower, <Callsign>, <Command>

DEPARTURE COMMANDS

PURPOSE	RECOGNIZED COMMAND
Ready	Request takeoff / ready for takeoff / ready for departure / number one
Holding short	Holding short [runway] One Four / Three Two
Climb	Request [unrestricted / quick] climb to / through <Altitude>
Helicopter	Request hover check / request takeoff from parking

PATTERN AND LANDING

PURPOSE	RECOGNIZED COMMAND
Initial / overhead	Initial / at initial / request the overhead / request initial / ready overhead
Special pattern	Request high tactical initial / overhead; request SFO; high key; low key
Base call	Left / right base, <gear report>, <landing intention>
Mileage call	Three / five miles, <gear report>, <landing intention>
Straight-in	Request straight in / straight-in landing
Closed traffic	Request closed / closed traffic
Other	Extending downwind / missed approach / runway in sight / traffic in sight / no joy / say winds
EXAMPLE	
Silverbow Tower, Dodge Two One, left base, gear down, full stop	

04 NELLIS CONTROL - DEPARTURE

UHF 254.400 | VHF 119.350

STANDARD SPOKEN FORMAT
Nellis Control, <Callsign>, <Command>

INITIAL CONTACT AND STATUS

PURPOSE	RECOGNIZED COMMAND
Initial contact	Checking in
Altitude report	Airborne passing <Altitude> / passing <Altitude>
Waypoint report	Is / passing / reporting <Waypoint>
Radar identification	Flash
Approach request	Request approach

VECTOR REQUESTS

VECTOR FORMAT	
Nellis Control, <Callsign>, request vector to <Waypoint>	
PURPOSE	ACCEPTED WORDING
Vector request	Request vector / request vectors / request a vector
Destination link	To / for <Waypoint>

VALID DEPARTURE NAVPOINTS

GROUP	VALID NAVPOINTS
IFR departure fixes	ESSAA; JAYSN; LEAHI; Tonopah TACAN; STOFF
Local VFR routing	Runway 14 FAF; Runway 32 FAF

REPORTING FORMAT

WAYPOINT REPORT
Nellis Control, <Callsign>, reporting <Waypoint>
EXAMPLE
Nellis Control, Dodge Two One, airborne passing seven thousand

05 NELLIS CONTROL - APPROACH

UHF 254.400 | VHF 119.350 SFA UHF 343.725 | VHF 124.950

STANDARD SPOKEN FORMAT
Nellis Control, <Callsign>, <Command>

CHECK-IN AND RADAR STATUS

PURPOSE	RECOGNIZED COMMAND
Initial / IFR status	Checking in VFR / IFR; is up on frequency; cancel IFR; request IFR pickup
Waypoint report	Is / passing / reporting <Waypoint>
Radar recovery	Request back to radar; breaking out
Missed approach	Request missed approach / is missed approach / going missed approach
Visual contact	Runway in sight

SUPPORTED APPROACH REQUESTS

SERVICE	RECOGNIZED REQUEST
TACAN	Request TACAN / TACAN approach; request TACAN final / vectors to the TACAN final
ILS / LOC	Request ILS / ILS approach; request ILS final / request vectors to the ILS final
RNAV	Request RNAV / RNAV approach
PAR / GCA	Request PAR approach / request GCA / request a GCA pickup

OTHER APPROACH COMMANDS

PURPOSE	RECOGNIZED COMMAND
Other requests	Request departure; request closed / request closed traffic

VECTOR REQUESTS

VECTOR FORMAT	
Nellis Control, <Callsign>, request vector to <Waypoint>	
RUNWAY / APPROACH	VALID NAVPOINTS
Runway 14 TACAN	COPAR; LOZMO; HUGER
Runway 14 ILS / RNAV	JEPAR; JANAV; OSRIE
Runway 32 TACAN	HUBON; IRAVE; ITAVE; ITOGE
Runway 32 ILS / RNAV	JESVO; JIREM; DRAKO; PALAE; WATLU; RUDII; FALAK
EXAMPLE	
Nellis Control, Dodge Two One, request ILS approach	

06 CALLSIGN-ONLY COMMANDS

STANDARD SPOKEN FORMAT
<Callsign>, <Command>

FOLLOW-UP COMMANDS

PURPOSE	RECOGNIZED COMMAND
Pattern	Initial; ready overhead; high key; low key; extending downwind; request closed traffic
Landing	Left / right base, <gear report>, <landing intention>; three / five miles, <gear report>, <landing intention>
Radar	Missed approach; breaking out; request back to radar
Visual	Runway in sight; traffic in sight; no joy; say winds
Status	IFR / VFR
Report point	Reporting a valid Silverbow or Nellis Control waypoint
EXAMPLE	
Dodge Two One, runway in sight	