

AI_ATC

VoiceAttack

Installation Guide

Install, configure and verify VoiceAttack for use with the AI_ATC mission environment.

SETUP OVERVIEW

1	Install files Install VoiceAttack and copy the supplied sound files.
2	Configure VoiceAttack Import profiles, configure speech recognition and assign PTT.
3	Configure DCS Match the radio-menu command and protect external-view bindings.
4	Verify operation Set the airbase and callsign, then complete a radio check.
GUIDE	Complete the steps in order. Screenshots show the relevant controls and reference numbers used in the original guide.

PHASE 1

Install VoiceAttack and mission files

Prepare the application, audio files and supplied profiles.

1

Download and install VoiceAttack. <https://voiceattack.com/>

2

Add the sound files to the VoiceAttack install directory

Example C:\Program Files\VoiceAttack\Sounds

(Files included with AI_ATC download)

 RADIO_TRANS_END.wav RADIO_TRANS_END_ALTERNATE.wav RADIO_TRANS_START.wav


3

Start VoiceAttack and Import the Admin and AI_ATC profiles



4


Open the VoiceAttack settings menu (Spanner Icon)



PHASE 1 CONTINUED

Configure VoiceAttack Settings


Use the numbered screenshot references to complete the General settings.



5 Add the Admin profile to the list of Global profiles - **6**

6 Set the AI_ATC profile to load on Startup. - **5**

7 Add the HOTAS controller you want to use for your PTT (Push to Talk) button - **7**



PHASE 2


Configure speech recognition and PTT

Complete VoiceAttack audio setup, speech training and push-to-talk assignment.

8 Configure your microphone from the Audio tab - **3**


9 Complete the Windows Speech Engine from the recognition tab - **2** [Utilities >](#)

10 Return to the main VA screen, Open the Admin profile



11 Configure the PRESS and RELEASE options for your PTT button - **1**
(Note: You can have up to 4 PTT buttons configured, only one is required)

☒ When I press button: Joystick 1 Button 16



12 If you're using a non-standard US keyboard, you can configure the Open Radio Menu command to match your keyboard. - **2**

Press Right Alt+\\ | keys and hold for 0.15 seconds and release

PHASE 3

Configure DCS controls

Match the radio-menu keybind and prevent VoiceAttack commands from activating external views.

13

Start DCS and open the Controls setup page. Ensure the Keyboard command in VoiceAttack (Right Alt + \) is the same as the (Call radio menu) keyboard command.

(Note: You will need to do this for Each module)

F/A-18C	All But Axis Commands	☐ Foldable view
Action	Category	Keyboard
COMM Switch - COMM 1 (call radio menu)	Throttle Grip, HOTAS	RAlt + \
COMM Switch - COMM 1 (VOIP)	Throttle Grip, HOTAS	
COMM Switch - COMM 2 (call radio menu)	Throttle Grip, HOTAS	RCtrl + \
COMM Switch - COMM 2 (VOIP)	Throttle Grip, HOTAS	
COMM Switch - MIDS A	Throttle Grip, HOTAS	
COMM Switch - MIDS B	Throttle Grip, HOTAS	

14

Add a modifier to the external view keyboard commands i.e (Left Alt) (Left Ctrl)

F1 Cockpit view	View	F1; LCtrl + F1
F1 Head shift movement on / off	View	LWin + F1
F1 HUD only view switch	View	LAlt + F1
F1 Natural head movement view	View	
F10 Map. Jump to view over current point	View	
F10 Theater map view	View	LCtrl + F10
F11 Airport free camera	View	LAlt + F11
F11 Camera moving backward	View	LAlt + Num/
F11 Camera moving forward	View	LAlt + Num*
F11 Jump to free camera	View	LCtrl + F11
F12 Civil traffic view	View	
F12 Static object view	View	LCtrl + F12
F12 Trains/cars toggle	View	LShift + F12
F2 Aircraft view	View	LCtrl + F2
F2 Toggle camera position	View	RAlt + F2
F2 Toggle local camera control	View	LAlt + F2
F2 View own aircraft	View	
F3 Fly-By jump view	View	
F3 Fly-By view	View	LCtrl + F3
F4 Arcade Chase view	View	LShift + F4
F4 Camera mounted on object	View	LCtrl + F4
F4 Chase view	View	
F5 Ground hostile view	View	
F5 nearest AC view	View	LCtrl + F5
F6 Released weapon view	View	LCtrl + F6
F6 Weapon to target view	View	
F7 Ground unit view	View	LCtrl + F7
F9 Landing signal officer view	View	LAlt + F9
F9 Ship view	View	LCtrl + F9

CHECK

The VoiceAttack radio-menu command and the DCS “Call radio menu” binding must match for each aircraft module you use.

Press Right Alt+\ | keys and hold for 0.15 seconds and release

COMM Switch - COMM 1 (call radio menu)

Throttle Grip, HOTAS

RAlt + \

PHASE 4

Verify the VoiceAttack profile

Confirm that the active profile recognizes the airbase and callsign commands.


15 Ensure the AI_ATC profile is active in VoiceAttack

Profile AI_ATC_v1.00

VOICE COMMAND

Depress your PTT switch and Say: **“Set Airbase to Nellis”**

You should see the command execute in the VoiceAttack Event Log Window




16 Set your preferred Callsign: (Note: There's 70 different callsigns VoiceAttack can recognise.)

VOICE COMMAND

Depress your PTT switch and Say: **“Set Callsign Hornet 1-1”**

You should see the Callsign set in the VoiceAttack Event Log Window



PHASE 5

Complete the in-mission radio check

Power the aircraft radios, tune the ground frequency and verify that the controller responds.

17

Start up the AI_ATC mission in DCS. Get the Aircraft radios powered up and tune your radio to the Ground Controller (UHF channel 3). Depress and hold the PTT button and say:

RADIO TRANSMISSION

“Nellis Ground, Hornet 1-1, Request engine start”

If you have set everything up correctly, The Controller will respond to your request.

REFERENCE

For a complete list of recognized commands, refer to the VoiceAttack Commands.PDF included with the downloaded .zip

SUPPORT

If you are having trouble with VoiceAttack, please don't hesitate to ask for Help on the AI_ATC Discord:

<https://discord.gg/JreGNfpqKQ>