Definitions:

NOT AVAILABLE JUST YET!

Powershell Commands:

```
1
 2
    "Installation DHCP:"
   Install-WindowsFeature dhcp -IncludeManagementTools
   "T2aked beli DHCP installer:"
   Get-WindowsFeature dhcp
   "Mn wra installation khass redemarrer:"
 8
   Restart-Computer
 9
10
    "Ajouter un nouveau scope:"
11
12 Add-DhcpServerv4Scope -Name "scope1" -StartRange 192.168.0.100 -EndRange 192.168.0.200
-SubnetMask 255.255.255.0
   Mni kadir chi Scope jdid kate3tah Id ex...
   ...-StartRange 172.128.6.100 -EndRange 172.128.6.200 -SubnetMask 255.255.255.0...
15
   ScopeID => 172.128.6.0
16
17
    "Ajouter la duree du bail (lease duration):"
   Set-DhcpServerv4Scope -ScopeId 192.168.0.0 -LeaseDuration 4.12:00:00
   LeaseDuration => jour.heures:minutes:second
19
20
    "Activer (active) / Desactiver (inActive) Scope:"
21
   Set-DhcpServerv4Scope -ScopeId 192.168.0.0 -State inActive
22
23
24
   "Afficher tout les Scopes:"
25
   Get-DhcpServerv4Scope
26
    "Ajouter une plage d exclusion (exclusion range):"
   Add-DhcpServerv4ExclusionRange -ScopeId 192.168.0.0 -StartRange 192.168.0.1010 -EndRange
192.168.0.125
29
   "Afficher toutes les plages d exclusion (Exclusion Ranges):"
30
```

```
31 Get-DhcpServerv4ExclusionRange
32
33
   "Ajouter des options a un Scope:"
   Ga3 les option dyal scope t9der tzid ola modifihom, hado des exemples:
   Set-DhcpServerv4OptionValue -ScopeId 192.168.0.0 -Router 192.168.0.254 -DnsServer
192.168.0.253 -DnsDomain "ofppt.local" -WinsServer 192.168.0.252
36
   "Afficher toutes les options disponibles pour un scope:"
37
   Get-DhcpServerv4OptionDefinition
39
40
    "Ajouter une reservation:"
  Add-DhcpServerv4Reservation -ScopeId 192.168.0.0 -IpAddress 192.168.0.101 -ClientId
"99:74:FE:A1:BB:69"
42
43
    "Redemarrer le service DHCP:"
44
   Restart-Service dhcpserver
45
    "Autoriser un serveur DHCP dans active directory:"
46
   Add-DhcpServerInDC -IpAddress 192.168.0.253 -DnsName "PC1.ofppt.local"
47
48
49
   Restart-Computer = restart-computer = RESTART-COMPUTER
```

Command Line Commands:

```
1
   "Configurez le serveur DHCP en utilisant la ligne de commande:"
 2
   sc config dhcpserver start=auto
   net start dhcpserver
6
   "Autorisez le serveur dans AD:"
   netsh dhcp add server Server1.ofppt.local 192.168.0.1
8
   "Créez un scope vide:"
10
11
   netsh dhcp server add scope 192.168.0.0 255.255.255.0 "Scope1"
12
   "Ajoutez une plage d'adresses IP:"
13
   netsh dhcp server scope 192.168.0.0 add iprange 192.168.0.10 192.168.0.100
```

```
16 "Définissez l'option de passerelle par défaut:"
   netsh dhcp server scope 192.168.0.0 set optionvalue 003 IPADDRESS 192.168.0.1
17
18
19 "Définissez la durée du bail en secondes:"
20 netsh dhcp server scope 192.168.0.0 set optionvalue 51 DWORD 28800
21
22 "Définissez le serveur DNS:"
23 netsh dhcp server scope 192.168.0.0 set optionvalue 006 IPADDRESS 192.168.0.1
24
25 "Ajoutez une réservation DHCP:"
26 netsh dhcp server scope 192.168.0.0 add reservedip 192.168.0.5 A1B2C3D4E5F6 "Printer1"
"Reservation for Printer1"
28 "Affiche tous les serveurs DHCP dans le service d'annuaire pour le domaine actuel:"
29 netsh dhcp show server
30
```