Practical 2:


EC2 > Instances > Launch an instance
Launch an instance
Amazon EC2 allows you to create virtual machines, or instances, that run on the AWS Cloud. Quickly get started by following the simple steps below.
Name and tags
Name
my-first-ec2
Add additional tags
Application and OS Images (Amazon Machine Image)
An AMI contains the operating system, application server, and applications for your instance. If you don't see a suitable AMI below, use the search field or choose Browse more AMIs.
Search our full catalog including 1000s of application and OS images
Recents
Quick Start
Amazon Linux
macOS
Ubuntu
Windows
Red Hat
SUSE Linux
Debian
Browse more AMIs
Including AMIs from AWS, Marketplace and the Community
Amazon Machine Image (AMI)
Amazon Linux 2023 kernel-6.1 AMI
Free tier eligible
Description
Summary
Number of instances
1
Software Image (AMI)
Amazon Linux 2023 AMI 2023.11...read more
Virtual server type (instance type)
t3.micro
Firewall (security group)
New security group
Storage (volumes)
1 volume(s) - 8 GiB
Cancel
Launch instance
Preview code


EC2 > Instances > Launch an instance
Amazon Machine Image (AMI)
Amazon Linux 2023 kernel-6.1 AMI
Free tier eligible
Description
Amazon Linux 2023 (kernel-6.1) is a modern, general purpose Linux-based OS that comes with 5 years of long term support. It is optimized for AWS and designed to provide a secure, stable and high-performance execution environment to develop and run your cloud applications.
Amazon Linux 2023 AMI 2023.11.20260413.0 x86_64 HVM kernel-6.1
Architecture
64-bit (x86)
Boot mode
uefi-preferred
AMI ID
ami-0a0823e4ea064404d
Publish Date
2026-04-10
Username
ec2-user
Verified provider
Instance type
Instance type
t3.micro
Free tier eligible
All generations
Compare instance types
Additional costs apply for AMIs with pre-installed software
Key pair (login)
You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.
Key pair name - required
Ec-2-key-pair
Create new key pair
Summary
Number of instances
1
Software Image (AMI)
Amazon Linux 2023 AMI 2023.11...read more
Virtual server type (instance type)
t3.micro
Firewall (security group)
New security group
Storage (volumes)
1 volume(s) - 8 GiB
Cancel
Launch instance
Preview code


EC2 > Instances > Launch an instance
Additional costs apply for AMIs with pre-installed software
Key pair (login) Info
You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.
Key pair name - required
Ec-2-key-pair
Create new key pair
Network settings Info
Edit
Network Info
vpc-070e3cb1a4f62aff05
Subnet Info
No preference (Default subnet in any availability zone)
Auto-assign public IP Info
Enable
Firewall (security groups) Info
A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.
Create security group
Select existing security group
We'll create a new security group called 'launch-wizard-3' with the following rules:
Allow SSH traffic from
Helps you connect to your instance
Anywhere
0.0.0.0/0
Allow HTTPS traffic from the internet
To set up an endpoint, for example when creating a web server
Allow HTTP traffic from the internet
Summary
Number of instances Info
1
Software Image (AMI)
Amazon Linux 2023 AMI 2023.11....read more
Virtual server type (instance type)
t3.micro
Firewall (security group)
New security group
Storage (volumes)
1 volume(s) - 8 GiB
Cancel
Launch instance
Preview code


EC2 > Instances > Launch an instance
Create security group
Select existing security group
We'll create a new security group called 'launch-wizard-3' with the following rules:
Allow SSH traffic from
Helps you connect to your instance
My IP
122.162.146.232/32
Allow HTTPS traffic from the internet
To set up an endpoint, for example when creating a web server
Allow HTTP traffic from the internet
To set up an endpoint, for example when creating a web server
Configure storage Info
Advanced
1x 8 GiB gp3 Root volume, 3000 IOPS, Not encrypted
Add new volume
Click refresh to view backup information
The tags that you assign determine whether the instance will be backed up by any Data Lifecycle Manager policies.
File systems
S3 Files - new
EFS
FSx
Advanced details Info
Summary
Number of instances Info
1
Software Image (AMI)
Amazon Linux 2023 AMI 2023.11....read more
Virtual server type (instance type)
t3.micro
Firewall (security group)
New security group
Storage (volumes)
1 volume(s) - 8 GiB
Cancel
Launch instance
Preview code


EC2 > Instances
EC2
Dashboard
AWS Global View
Events
Instances
Instances
Instance Types
Launch Templates
Spot Requests
Savings Plans
Reserved Instances
Dedicated Hosts
Capacity Reservations
Capacity Manager New
Images
AMIs
AMI Catalog
Elastic Block Store
Volumes
Snapshots
Lifecycle Manager
Network & Security
Security Groups
Elastic IPs
Placement Groups
Instances (1/6) Info
Connect
Instance state
Actions
Launch instances
Name
Instance ID
Instance state
Instance type
Status check
Alarm status
Availability Zone
Public IPv4 DNS
Public IPv4 ...
MyFirstEc2
i-06fdf78d014f16a73
Terminated
t3.micro
eu-north-1c
my-first-ec2
i-07adc3fee68ccfd7a
Running
t3.micro
Initializing
eu-north-1b
ec2-13-48-205-198.eu-...
13.48.205.19
i-06490cf228ae2c3ad
Terminated
t3.micro
eu-north-1b
private-ec2-new
i-0899e86e5a7a7610f
Terminated
t3.micro
eu-north-1a
public-ec2-new
i-092635cfa58cac3a6
Terminated
t3.micro
eu-north-1a
i-08637c5b0550fb69f
Terminated
t3.micro
eu-north-1a
i-07adc3fee68ccfd7a (my-first-ec2)
Details
Status and alarms
Monitoring
Security
Networking
Storage
Tags
Instance summary Info
Instance ID
i-07adc3fee68ccfd7a
IPv6 address
Hostname type
Public IPv4 address
13.48.205.198 | open address
Instance state
Running
Private IP DNS name (IPv4 only)
Private IPv4 addresses
172.31.39.59
Public DNS
ec2-13-48-205-198.eu-north-1.compute.amazonaws.com | open address


EC2 > Security Groups > sg-0f083a371bcc0c520 - launch-wizard-3 > Edit inbound rules
Edit inbound rules Info
Inbound rules control the incoming traffic that's allowed to reach the instance.
Inbound rules Info
Security group rule ID
sgr-0bed2ddec08b5adb8
Type Info
SSH
Protocol Info
TCP
Port range Info
22
Source Info
My IP
122.162.146.232/32
Description - optional Info
Delete
Add rule
Cancel
Preview changes
Save rules


EC2 > Instances
Instances (1/1)
Connect
Instance state
Actions
Launch instances
my-first-ec2
i-0c5ae311b3248c2e3
Running
ec2-54-146-4-94.comp...
54.146.4.94
Amazon Linux 2023
https://aws.amazon.com/linux/amazon-linux-2023
i-0c5ae311b3248c2e3 (my-first-ec2)
Details
Status and alarms
Monitoring
Security
Networking
Storage
Tags
Instance summary
Instance ID
i-0c5ae311b3248c2e3
IPv6 address
Hostname type
Answer private resource DNS name
54.146.4.94
Instance state
Running
Private IP DNS name (IPv4 only)
ip-172-31-34-1.ec2.internal
Instance type
t3.micro
Private IPv4 addresses
172.31.34.1
Public DNS
ec2-54-146-4-94.compute-1.amazonaws.com
Elastic IP addresses

Practical 3:


Launch an instance
Name and tags
Name
public-ec2
Add additional tags
Application and OS Images (Amazon Machine Image)
Recents
Quick Start
Amazon Linux
macOS
Ubuntu
Windows
Red Hat
SUSE Linux
Debian
Browse more AMIs
Amazon Machine Image (AMI)
Amazon Linux 2023 kernel-6.1 AMI
Free tier eligible
Description
Summary
Number of instances
Software Image (AMI)
Virtual server type (instance type)
t3.micro
Firewall (security group)
New security group
Storage (volumes)
1 volume(s) - 8 GiB
Cancel
Launch instance
Preview code


EC2 > Instances > Launch an instance
Instance type
t3.micro
Free tier eligible
All generations
Compare instance types
Additional costs apply for AMIs with pre-installed software
Key pair (login)
Key pair name - required
Ec-2-key-pair
Create new key pair
Network settings
VPC - required
vpc-0de7a9ebf847753d2 (my-custom-vpc)
Subnet
subnet-0b1eb21b28e147ac4
public-subnet-1
Create new subnet
Auto-assign public IP
Enable
Firewall (security groups)
Summary
Number of instances
1
Software image (AMI)
Amazon Linux 2023 AMI 2023.11....read more
Virtual server type (instance type)
t3.micro
Firewall (security group)
New security group
Storage (volumes)
1 volume(s) - 8 GiB
Cancel
Launch instance
Preview code


EC2 > Instances > Launch an instance
Create security group
Select existing security group
Security group name - required
launch-wizard-7
Description - required
launch-wizard-7 created 2026-04-21T07:59:10.564Z
Inbound Security Group Rules
Remove
Type
ssh
Protocol
TCP
Port range
22
Source type
My IP
Name
Description - optional
e.g. SSH for admin desktop
Remove
Type
HTTP
Protocol
TCP
Port range
80
Source type
Anywhere
Source
0.0.0.0/0
Summary
Number of instances
1
Software image (AMI)
Amazon Linux 2023 AMI 2023.11....read more
Virtual server type (instance type)
t3.micro
Firewall (security group)
New security group
Storage (volumes)
1 volume(s) - 8 GiB
Cancel
Launch instance
Preview code


Your VPCs
VPCs
VPC encryption controls
Your VPCs (1/2)
Actions
Create VPC
Name
VPC ID
State
Encryption c...
Encryption control ...
Block Public...
IPv4 CIDR
IPv6
vpc-070e3cb1a4f62ef05
Available
Off
172.31.0.0/16
vpc-0de7a9ebf847753d2 / my-custom-vpc
Details
Resource map
CIDRs
Flow logs
Tags
Integrations
Details
VPC ID
vpc-0de7a9ebf847753d2
State
Available
Block Public Access
Off
DNS hostnames
Enabled
DNS resolution
Enabled
Tenancy
default
DHCP option set
dopt-002f151a4dd10528a
Main route table
rtb-06f460edfdce851c4
Main network ACL
acl-0182c6cb0ca797882
Default VPC
No
IPv4 CIDR
10.0.0.0/16
IPv6 pool
IPv6 CIDR (Network border group)
Network Address Usage metrics
Disabled
Route 53 Resolver DNS Firewall rule groups
Owner ID
649631967305
Encryption control ID
Encryption control mode
Virtual private cloud
Your VPCs
Subnets
Route tables
Internet gateways
Egress-only internet gateways
DHCP option sets
Elastic IPs
Managed prefix lists
NAT gateways
Peering connections
Route servers
Security
Network ACLs
Security groups
PrivateLink and Lattice
Getting started
Endpoints
Endpoint services
Service networks
Lattice services
Resource configurations
Resource gateways


Internet gateways (1/1)
Actions
Create internet gateway
Name
Internet gateway ID
State
VPC ID
Owner
my-igw
igw-087b5743fef5390b0
Attached
649631967305
igw-087b5743fef5390b0 / my-igw
Details
Tags
Details
Internet gateway ID
igw-087b5743fef5390b0
State
Attached
VPC ID
vpc-0de7a9ebf847753d2 | my-custom-vpc
Owner
649631967305
Virtual private cloud
Your VPCs
Subnets
Route tables
Internet gateways
Egress-only internet gateways
DHCP option sets
Elastic IPs
Managed prefix lists
NAT gateways
Peering connections
Route servers
Security
Network ACLs
Security groups
PrivateLink and Lattice
Getting started
Endpoints
Endpoint services
Service networks
Lattice services
Resource configurations
Resource gateways


VPC > Route tables
Route tables (1/4) Info
Actions
Create route table
Filter by VPC
Virtual private cloud
Your VPCs
Subnets
Route tables
Internet gateways
Egress-only internet gateways
DHCP option sets
Elastic IPs
Managed prefix lists
NAT gateways
Peering connections
Route servers
Security
Network ACLs
Security groups
PrivateLink and Lattice
Getting started
Endpoints
Endpoint services
Service networks
Lattice services
Resource configurations
Resource gateways
Name
Route table ID
Explicit subnet associ...
Edge associations
Main
VPC
Owner ID
public-rt
rtb-052d116df2bfa3420
2 subnets
No
649631967305
private-rt
rtb-0d1b2b1358d0aadd0
Yes
rtb-052d116df2bfa3420 / public-rt
Details
Routes
Subnet associations
Edge associations
Route propagation
Tags
Route table ID
rtb-052d116df2bfa3420
Main
No
Owner ID
649631967305
VPC
vpc-0de7a9ebf847755d2 | my-custom-vpc
Explicit subnet associations
2 subnets
Edge associations
Activate Windows


VPC > NAT gateways
NAT gateways (1/1) Info
Actions
Create NAT gateway
Egress-only internet gateways
DHCP option sets
Elastic IPs
Managed prefix lists
NAT gateways
Peering connections
Route servers
Security
Network ACLs
Security groups
PrivateLink and Lattice
Getting started
Endpoints
Endpoint services
Service networks
Lattice services
Resource configurations
Resource gateways
Target groups
Domain verifications New
DNS firewall
Rule groups
Domain lists
Network Firewall
Name
NAT gateway ID
Connectivity...
State
State message
Availability ...
Route table ID
Primary public I...
my-nat-gw
nat-00604039cc0bef2bd
Public
Available
Zonal
13.53.161.222
nat-00604039cc0bef2bd / my-nat-gw
Details
Secondary IPv4 addresses
Monitoring
Tags
NAT gateway ID
nat-00604039cc0bef2bd
NAT gateway ARN
arn:aws:ec2:eu-north-1:649631967305:natgateway/nat-00604039cc0bef2bd
VPC
vpc-0de7a9ebf847755d2 / my-custom-vpc
Connectivity type
Public
Primary public IPv4 address
13.53.161.222
Subnet
subnet-0b1eb21b28e147ac4 / public-subnet-1
State
Available
Primary private IPv4 address
10.0.1.31
Created
Monday, April 20, 2026 at 06:37:05 GMT+5:30
State message
Primary network interface ID
eni-0ee5860b6cda1b3e5
Deleted
Activate Windows


Route tables (1/4)
Actions
Create route table
Name
Route table ID
Explicit subnet associ...
Edge associations
Main
VPC
Owner ID
public-rt
rtb-052d136df2bfa3420
2 subnets
No
649631967305
private-rt
rtb-0022ffb669818f8a8
subnet-0613c77eb01df4...
rtb-06f460edfdce331c4
rtb-0d1b2b1358d0aadd0
rtb-0022ffb669818f8a8 / private-rt
Details
Routes
Subnet associations
Edge associations
Route propagation
Tags
Route table ID
Main
Explicit subnet associations
subnet-0613c77eb01df4998 / private-subnet-1
Edge associations
VPC
vpc-0de7a9ebf847755d2 | my-custom-vpc
Owner ID
649631967305


Instances (1/3)
Connect
Instance state
Actions
Launch instances
Status check
Alarm status
Availability Zone
Public IPv4 DNS
View alarms
eu-north-1b
eu-north-1a
ec2-16-171-256-3.eu-n...
16.171.256.3
i-0c7f9413200416567 (private-ec2)
Details
Status and alarms
Monitoring
Security
Networking
Storage
Tags
Instance summary
Instance ID
i-0c7f9413200416567
Public IPv4 address
Private IPv4 address copied
10.0.1.170
IPv6 address
Instance state
Public DNS

Practical 4:


Create launch template
Creating a launch template allows you to create a saved instance configuration that can be reused, shared and launched at a later time. Templates can have multiple versions.
Launch template name and description
Launch template name - required
my-template
Template version description
A prod webserver for MyApp
Auto Scaling guidance
Provide guidance to help me set up a template that I can use with EC2 Auto Scaling
Template tags
Source template
Launch template contents
Specify the details of your launch template below. Leaving a field blank will result in the field not being included in the launch template.
Application and OS Images (Amazon Machine Image)
Summary
Software Image (AMI)
Amazon Linux 2023 kernel-6.1 A...read more
Virtual server type (instance type)
t3.micro
Firewall (security group)
my-ec2-sg
Storage (volumes)
1 volume(s) - 8 GiB
Cancel
Create launch template


EC2 > Launch templates > my-template
my-template (lt-07544d0d29a91870b)
Actions
Delete template
Launch template details
Launch template ID
lt-07544d0d29a91870b
Launch template name
my-template
Default version
1
Owner
Details
Versions
Template tags
Launch template version details
Actions
Delete template version
Version
1 (Default)
Description
Date created
2026-04-20T13:52:27.000Z
Created by
Instance details
Storage
Resource tags
Network interfaces
Advanced details
AMI ID
ami-0a0823e4ea0644044
Instance type
t3.micro
Availability Zone
Availability Zone Id
Key pair name
Security groups
Security group IDs
EC2
Dashboard
AWS Global View
Events
Instances
Instances
Instance Types
Launch Templates
Spot Requests
Savings Plans
Reserved Instances
Dedicated Hosts
Capacity Reservations
Capacity Manager
Images
AMIs
AMI Catalog
Elastic Block Store
Volumes
Snapshots
Lifecycle Manager
Network & Security
Security Groups
Elastic IPs


EC2 > Auto Scaling groups > Create Auto Scaling group
Step 3 - optional
Integrate with other services
Step 4 - optional
Configure group size and scaling
Step 5 - optional
Add notifications
Step 6 - optional
Add tags
Step 7
Review
Instance type requirements Info
Override launch template
You can keep the same instance attributes or instance type from your launch template, or you can choose to override the launch template by specifying different instance attributes or manually adding instance types.
Launch template
my-template
lt-07544d0d29a91870b
Version
Latest
Description
Instance type
t3.micro
Network Info
For most applications, you can use multiple Availability Zones and let EC2 Auto Scaling balance your instances across the zones. The default VPC and default subnets are suitable for getting started quickly.
VPC
Choose the VPC that defines the virtual network for your Auto Scaling group.
vpc-0de7a9ebf847753d2 (my-custom-vpc)
10.0.0.0/16
Create a VPC
Availability Zones and subnets
Define which Availability Zones and subnets your Auto Scaling group can use in the chosen VPC.
Select Availability Zones and subnets
eun1-az1 (eu-north-1a) | subnet-0b1eb21b28e147ac4 (public-subnet-1)
10.0.1.0/24
eun1-az2 (eu-north-1b) | subnet-018af86c35540cf7f (public-02)
10.0.3.0/24
Create a subnet
Availability Zone distribution - new


EC2 > Auto Scaling groups > Create Auto Scaling group
Step 1
Choose launch template
Step 2
Choose instance launch options
Step 3 - optional
Integrate with other services
Step 4 - optional
Configure group size and scaling
Step 5 - optional
Add notifications
Step 6 - optional
Add tags
Step 7
Review
Integrate with other services - optional Info
Use a load balancer to distribute network traffic across multiple servers. Enable service-to-service communications with VPC Lattice. Shift resources away from impaired Availability Zones with zonal shift. You can also customize health check replacements and monitoring.
Load balancing Info
Use the options below to attach your Auto Scaling group to an existing load balancer, or to a new load balancer that you define.
Select Load balancing options
No load balancer
Traffic to your Auto Scaling group will not be fronted by a load balancer.
Attach to an existing load balancer
Choose from your existing load balancers.
Attach to a new load balancer
Quickly create a basic load balancer to attach to your Auto Scaling group.
Attach to a new load balancer
Load balancer type
Choose from the load balancer types offered below. Type selection cannot be changed after the load balancer is created. If you need a different type of load balancer than those offered here, visit the Load Balancing console.
Application Load Balancer
HTTP, HTTPS
Network Load Balancer
TCP, UDP, TLS
Load balancer name
Name cannot be changed after the load balancer is created.
web-alb
Must be unique within the Region. Use 1–32 alphanumeric characters and hyphens. Can't start with "internal-" or begin or end with a hyphen.
Load balancer scheme
Scheme cannot be changed after the load balancer is created.
Internal
Internet-facing
Network mapping
Your new load balancer will be created using the same VPC and Availability Zone selections as your Auto Scaling group. You can select different subnets and add subnets from additional Availability Zones.

EC2 > Auto Scaling groups > Create Auto Scaling group

VPC

vpc-0de7a9ebf847753d2 my-custom-vpc

Availability Zones and subnets

You must select a single subnet for each Availability Zone enabled. Only public subnets are available for selection to support DNS resolution.

eun1-az1 (eu-north-1a) — Select a subnet: subnet-0b1eb21b28e147ac4

eun1-az2 (eu-north-1b) — Select a subnet: subnet-01ba9B6c55540cf7f

Listeners and routing

If you require secure listeners, or multiple listeners, you can configure them from the Load Balancing console after your load balancer is created.

Protocol	Port	Default routing (forward to)
HTTP	80	Create a target group

New target group name

An instance target group with default settings will be created.

web-target-group

Must be unique within the Region. Use 1-32 alphanumeric characters and hyphens. Can't begin or end with a hyphen.

Tags - *optional*

Consider adding tags to your load balancer. Tags enable you to categorize your AWS resources so you can more easily manage them.

Add tag

50 remaining

VPC Lattice integration options Info

To improve networking capabilities and scalability, integrate your Auto Scaling group with VPC Lattice. VPC Lattice facilitates communications between AWS services and helps you connect and manage your applications across compute services in AWS.

Select VPC Lattice service to attach

EC2 > Auto Scaling groups > Create Auto Scaling group

Application Recovery Controller (ARC) zonal shift - *new* Info

During an Availability Zone impairment, target instance launches towards other healthy Availability Zones.

☐ Enable zonal shift

New instance launches will be retargeted towards healthy Availability Zones until the zonal shift is canceled.

Health checks

Health checks increase availability by replacing unhealthy instances. When you use multiple health checks, all are evaluated, and if at least one fails, instance replacement occurs.

EC2 health checks

Always enabled

Additional health check types - *optional* Info

☑ Turn on Elastic Load Balancing health checks Recommended

Elastic Load Balancing monitors whether instances are available to handle requests. When it reports an unhealthy instance, EC2 Auto Scaling can replace it on its next periodic check.

EC2 Auto Scaling will start to detect and act on health checks performed by Elastic Load Balancing. To avoid unexpected terminations, first verify the settings of these health checks in the Load Balancer console

☐ Turn on VPC Lattice health checks

VPC Lattice can monitor whether instances are available to handle requests. If it considers a target as failed a health check, EC2 Auto Scaling replaces it after its next periodic check.

☐ Turn on Amazon EBS health checks

EBS monitors whether an instance's root volume or attached volume stalls. When it reports an unhealthy volume, EC2 Auto Scaling can replace the instance on its next periodic health check.

Health check grace period Info

This time period delays the first health check until your instances finish initializing. It doesn't prevent an instance from terminating when placed into a non-running state.

300 seconds

Cancel | Skip to review | Previous | Next


vpc
Ask Amazon Q
Europe (Stockholm)
Dev
EC2 > Auto Scaling groups > Create Auto Scaling group
Step 1
Choose launch template
Step 2
Choose instance launch options
Step 3 - optional
Integrate with other services
Step 4 - optional
Configure group size and scaling
Step 5 - optional
Add notifications
Step 6 - optional
Add tags
Step 7
Review
Configure group size and scaling - optional Info
Define your group's desired capacity and scaling limits. You can optionally add automatic scaling to adjust the size of your group.
Group size Info
Set the initial size of the Auto Scaling group. After creating the group, you can change its size to meet demand, either manually or by using automatic scaling.
Desired capacity type
Choose the unit of measurement for the desired capacity value. vCPUs and Memory(GiB) are only supported for mixed instances groups configured with a set of instance attributes.
Units (number of instances)
Desired capacity
Specify your group size.
2
Scaling Info
You can resize your Auto Scaling group manually or automatically to meet changes in demand.
Scaling limits
Set limits on how much your desired capacity can be increased or decreased.
Min desired capacity
2
Equal or less than desired capacity
Max desired capacity
5
Equal or greater than desired capacity
Automatic scaling - optional
Choose whether to use a target tracking policy Info
You can set up other metric-based scaling policies and scheduled scaling after creating your Auto Scaling group.
No scaling policies
Your Auto Scaling group will remain at its initial size and will not dynamically resize to meet demand.
Target tracking scaling policy
Choose a CloudWatch metric and target value and let the scaling policy adjust the desired capacity in proportion to the metric's value.
CloudShell
Feedback
Console Mobile App
© 2026, Amazon Web Services, Inc. or its affiliates.
Privacy
Terms
Cookie preferences
Type here to search


vpc
Ask Amazon Q
Europe (Stockholm)
Dev
EC2 > Auto Scaling groups > Create Auto Scaling group
Step 1
Choose launch template
Step 2
Choose instance launch options
Step 3 - optional
Integrate with other services
Step 4 - optional
Configure group size and scaling
Step 5 - optional
Add notifications
Step 6 - optional
Add tags
Step 7
Review
Configure group size and scaling - optional Info
Define your group's desired capacity and scaling limits. You can optionally add automatic scaling to adjust the size of your group.
Group size Info
Set the initial size of the Auto Scaling group. After creating the group, you can change its size to meet demand, either manually or by using automatic scaling.
Desired capacity type
Choose the unit of measurement for the desired capacity value. vCPUs and Memory(GiB) are only supported for mixed instances groups configured with a set of instance attributes.
Units (number of instances)
Desired capacity
Specify your group size.
2
Scaling Info
You can resize your Auto Scaling group manually or automatically to meet changes in demand.
Scaling limits
Set limits on how much your desired capacity can be increased or decreased.
Min desired capacity
2
Equal or less than desired capacity
Max desired capacity
5
Equal or greater than desired capacity
Automatic scaling - optional
Choose whether to use a target tracking policy Info
You can set up other metric-based scaling policies and scheduled scaling after creating your Auto Scaling group.
No scaling policies
Your Auto Scaling group will remain at its initial size and will not dynamically resize to meet demand.
Target tracking scaling policy
Choose a CloudWatch metric and target value and let the scaling policy adjust the desired capacity in proportion to the metric's value.
Activate Windows
CloudShell
Feedback
Console Mobile App
© 2026, Amazon Web Services, Inc. or its affiliates.
Privacy
Terms
Cookie preferences
Type here to search


EC2 > Auto Scaling groups > Create Auto Scaling group
Automatic scaling - optional
Choose whether to use a target tracking policy
No scaling policies
Target tracking scaling policy
Scaling policy name
scale-on-cpu
Metric type
Average CPU utilization
Target value
70
Instance warmup
300
seconds
Disable scale in to create only a scale-out policy
Instance maintenance policy
Choose a replacement behavior depending on your availability requirements
No policy
Launch before terminating
Terminate and launch
Custom behavior


EC2 > Auto Scaling groups
Auto Scaling groups (1/1)
Launch configurations
Launch templates
Actions
Create Auto Scaling group
Name
Launch template/configuration
Instances
Status
Desired capacity
Min
Max
web-asg
my-template | Version Latest
2
-
2
2
5
Auto Scaling group: web-asg
Details
Integrations
Automatic scaling
Instance management
Instance refresh
Activity
Monitoring
Tags
Instances (2)
Instance ID
Lifecycle
Instance type
Weighted cap...
Launch templ...
Availability Z...
Health status
Protected from
i-06490cf228ae2c3ad
InService
t3.micro
Healthy
i-0863fcf6b0550fb6f
InService
t3.micro
Healthy
Instance lifecycle policy for lifecycle hooks
Manage policy
Termination hook abandon behavior
Terminate (default)
Capacity Reservations
Capacity Manager
Images
AMIs
AMI Catalog
Elastic Block Store
Volumes
Snapshots
Lifecycle Manager
Network & Security
Security Groups
Elastic IPs
Placement Groups
Key Pairs
Network Interfaces
Load Balancing
Load Balancers
Target Groups
Trust Stores
Auto Scaling
Auto Scaling Groups
Settings


EC2 > Load balancers
Load balancers (1/1)
Elastic Load Balancing scales your load balancer capacity automatically in response to changes in incoming traffic.
Actions
Create load balancer
Name
State
Type
Scheme
IP address type
VPC ID
Availability Zones
Security groups
web-alb
Active
application
Internet-facing
IPv4
vpc-0de7a9ebf847753d2
2 Availability Zones
Load balancer: web-alb
Details
Listeners and rules
Network mapping
Resource map
Security
Monitoring
Integrations
Attributes
Capacity
Tags
Load balancer type
Application
Status
Active
VPC
Load balancer IP address type
IPv4
Scheme
Internet-facing
Hosted zone
Availability Zones
Date created
April 20, 2026, 19:45 (UTC+05:30)
Load balancer ARN
DNS name


EC2 > Load balancers
Load balancers (1/1)
Elastic Load Balancing scales your load balancer capacity automatically in response to changes in incoming traffic.
Actions
Create load balancer
Name
State
Type
Scheme
IP address type
VPC ID
Availability Zones
Security groups
web-alb
Active
application
Internet-facing
IPv4
vpc-0de7a9ebf847753d2
2 Availability Zones
Load balancer: web-alb
Details
Listeners and rules
Network mapping
Resource map
Security
Monitoring
Integrations
Attributes
Capacity
Tags
Listeners and rules (1)
A listener checks for connection requests on its configured protocol and port. Traffic received by the listener is routed according to the default action and any additional rules.
Manage rules
Manage listener
Add listener
Protocol:Port
Default action
Rules
ARN
Security policy
Default SSL/TLS certificate
mTLS
HTTP:80
Forward to target group
web-alb-target-group: 1 (100%)
Target group stickiness: Off
1 rule
ARN
Not applicable
Not applicable
Not applicable


EC2 > Target groups > web-alb-target-group
web-alb-target-group
Actions
Details
Target type
Instance
Protocol : Port
HTTP: 80
Protocol version
HTTP1
VPC
IP address type
IPv4
Load balancer
web-alb
2
Total targets
2
Healthy
0 Anomalous
0
Unhealthy
0
Unused
0
Initial
0
Draining
Distribution of targets by Availability Zone (AZ)
Targets
Monitoring
Health checks
Attributes
Tags
Registered targets (2)
Anomaly mitigation: Not applicable
Deregister
Register targets
Target groups route requests to individual registered targets using the protocol and port number specified. Health checks are performed on all registered targets according to the target group's health check settings.
Anomaly detection is automatically applied to HTTP/HTTPS target groups with at least 5 healthy targets.
Filter targets
Instance ID
Name
Port
Zone
Health status
Health status details
Adminis...
Overrid...
Launch...
80
Healthy
No override...
No override
April 20, 2...

Not secure
🚀 Auto Scaling is Working!
Instance ID:
Availability Zone:
Refresh to see load balancing distribute to different instances

Practical 5:


Amazon S3
Buckets
General purpose buckets
Directory buckets
Table buckets
Vector buckets
Files
File systems
Access management and security
Access Points
Access Points for FSx
Access Grants
IAM Access Analyzer
Storage management and insights
Storage Lens
Batch Operations
Account and organization settings
AWS Marketplace for S3
Buckets
General purpose buckets
All AWS Regions
Directory buckets
General purpose buckets (1)
Buckets are containers for data stored in S3.
Copy ARN
Empty
Delete
Create bucket
Find buckets by name
Name
AWS Region
Creation date
ayu-bacic-web-2026-mr
Europe (Stockholm) eu-north-1
April 19, 2026, 21:49:02 (UTC+05:30)
Account snapshot
View dashboard
Updated daily
Storage Lens provides visibility into storage usage and activity trends.
External access summary
Updated daily
External access findings help you identify bucket permissions that allow public access or access from other AWS accounts.


Amazon S3
Buckets
ayu-bacic-web-2026-mr
ayu-bacic-web-2026-mr
Objects
Metadata
Properties
Permissions
Metrics
Management
File systems - new
Access Points
Objects (3)
Copy S3 URI
Copy URL
Download
Open
Delete
Actions
Create folder
Upload
Objects are the fundamental entities stored in Amazon S3. You can use Amazon S3 inventory to get a list of all objects in your bucket. For others to access your objects, you'll need to explicitly grant them permissions. Learn more
Find objects by prefix
Name
Type
Last modified
Size
Storage class
error.html
html
April 19, 2026, 21:49:41 (UTC+05:30)
165.0 B
Standard
index.html
html
April 19, 2026, 21:49:42 (UTC+05:30)
568.0 B
Standard
style.css
css
April 19, 2026, 21:49:42 (UTC+05:30)
471.0 B
Standard



My Cloud-Hosted Website

This website is hosted on **AWS S3**

No servers needed — just pure cloud storage!

Learn More

Activate Windows
Go to Settings to activate Windows.