Analyse-DLS-with-CONTIN

Ingo Breßler

May 09, 2022

Contents:

1 Attenuation specified in sample description

1

1 Attenuation specified in sample description

dlshelpers.getAttenuationFromMemo(memo, count=4, detectorKey='detektor', levelKey='stufe', key=None)

Extract manually specified attenuation of individual scattering angles from a given measurement data files (ASC) *SampMemo* field. Different notations and numbers of detectors are accepted (test cases):

```
>>> getAttenuationFromMemo("Toluolmessung für Statik,, Detektor 1 und 2, 1 Stufe...

-- abgeschwächt")
[0.1, 0.3, 1.0, 1.0]
```

```
>>> getAttenuationFromMemo("Toluolmessung für Statik,, Detektor 1 und 2, 1 Stufe⊔

→abgeschwächt, Detektor 3 , 2 Stufen abgeschwächt")

[0.1, 0.3, 0.1, 1.0]
```

```
>>> getAttenuationFromMemo("Toluolmessung für Statik,, Detektor 1 und 2, 1 Stufe_ abgeschwächt, Detektor 3 und 4, 2 Stufen abgeschwächt")
[0.1, 0.3, 0.1, 0.1]
```

```
>>> getAttenuationFromMemo("Toluolmessung für Statik,, Detektor 1, 1 Stufe...

--abgeschwächt, Detektor 3 , 2 Stufen abgeschwächt")

[0.1, 1.0, 0.1, 1.0]
```

```
>>> getAttenuationFromMemo("1:100 verdünnt mit Wasser, ungefiltert,, Detektor 1(10 

->%) und 2(30%), 1 Stufe abgeschwächt")
[0.1, 0.3, 1.0, 1.0]
```

Table of transmission levels 1-4 (columns) as defined in the program for detectors 1-4 (rows): >>> print(transmissionLevels) [[1. 0.1 0.03 0.01]

```
[1. 0.3 0.1 0.03] [1. 0.3 0.1 0.03] [1. 0.3 0.1 0.03]]
```