

```
ROUTER#disable
ROUTER>enable
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#exit
ROUTER#
*Aug 18 11:33:14.841: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              unassigned      YES TFTP    up          up
Ethernet0/1              unassigned      YES TFTP    down        down
Ethernet0/2              unassigned      YES TFTP    down        down
Ethernet0/3              unassigned      YES TFTP    down        down
ROUTER#interface ethernet 0/0
^
% Invalid input detected at '^' marker.
```

```
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#shutdown
ROUTER(config-if)#
```

```
*Aug 18 11:37:29.716: %LINK-5-CHANGED: Interface Ethernet0/0, changed state to administratively down
Router # configure terminal ( To move from privilege to g
Router(config)# Interface ethernet 0/0 ( To select interface )
```

```

e to down
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Aug 18 11:38:11.040: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip int brief
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              unassigned      YES TFTP   administratively down down
Ethernet0/1              unassigned      YES TFTP   down        down
Ethernet0/2              unassigned      YES TFTP   down        down
Ethernet0/3              unassigned      YES TFTP   down        down
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#
*Aug 18 11:40:06.177: %LINK-3-UPDOWN: Interface Ethernet0/0, changed state to up
ROUTER(config-if)#
*Aug 18 11:40:07.177: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up
ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#

```

```

Router # configure terminal      ( To move from privilege to global configuration mode )
Router(config)# interface ethernet 0/0  ( To select interface )
Router(config-if)# ip address 50.0.0.1 255.0.0.0  ( To assign ip address )

```

ROUTER

```
ROUTER#show ip int brief
Interface
Ethernet0/0      50.0.0.1      YES manual up      Protocol
Ethernet0/1      unassigned    YES TFTP  down    up
Ethernet0/2      unassigned    YES TFTP  down    down
Ethernet0/3      unassigned    YES TFTP  down    down
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#username boobathi password 8072408599
ROUTER(config)#line console 0
ROUTER(config-line)#login local
ROUTER(config-line)#exit
^
% Invalid input detected at '^' marker.
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
*Aug 18 11:47:32.167: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#exit
```

Router # configure terminal

Router(config)# interface ethernet 0/0

Router(config-if)# ip address 50.0.0.1 255.0.0.0

Router(config-if)# no shutdown

(To move from privilege to global configuration mode)

(To select interface)

(To assign ip address)

(To enable interface)

Redmi 13C 5G

Accessibility

ROUTER con0 is now available

Press RETURN to get started.

User Access Verification

Username: boobathi

Password:

% Login invalid

Username: boobathi

Password:

ROUTER>

```
ROUTER
% Login invalid

Username: boobathi
Password:
ROUTER>enable
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#password 8072408599
      ^
% Invalid input detected at '^' marker.

ROUTER(config)#line console 0
ROUTER(config-line)#password 8072408599
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
*Aug 18 11:53:03.147: %SYS-5-CONFIG_I: Configured from console by boobathi on console
ROUTER#exit
```