

```

Router>
Router>
Router>
Router>
Router>
Router>enable
Router#
Router#
Router#
Router#config ter
Router#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#disable
Router>
Router>
Router>sh ip int br
Router>sh ip int brief


```

| Interface       | IP-Address | OK? | Method | Status                | Protocol |
|-----------------|------------|-----|--------|-----------------------|----------|
| FastEthernet0/0 | unassigned | YES | unset  | administratively down | down     |
| FastEthernet0/1 | unassigned | YES | unset  | administratively down | down     |
| Ethernet1/0     | unassigned | YES | unset  | administratively down | down     |
| Ethernet1/1     | unassigned | YES | unset  | administratively down | down     |
| Ethernet1/2     | unassigned | YES | unset  | administratively down | down     |
| Ethernet1/3     | unassigned | YES | unset  | administratively down | down     |

```

Router>

```



```

Router#sh ip int brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 50.0.0.1        YES manual down        down
FastEthernet0/1 unassigned      YES unset   administratively down down
Ethernet1/0     unassigned      YES unset   administratively down down
Ethernet1/1     unassigned      YES unset   administratively down down
Ethernet1/2     unassigned      YES unset   administratively down down
Ethernet1/3     unassigned      YES unset   administratively down down
Router#
Router#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router#
Router#sh ip int brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 50.0.0.1        YES manual up          up
FastEthernet0/1 unassigned      YES unset   administratively down down
Ethernet1/0     unassigned      YES unset   administratively down down
Ethernet1/1     unassigned      YES unset   administratively down down
Ethernet1/2     unassigned      YES unset   administratively down down
Ethernet1/3     unassigned      YES unset   administratively down down
Router#
Router#

```

```
Router(config)#username babin password babin
Router(config)#line console 0
Router(config-line)#login local
Router(config-line)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#
Router#exit
```

Router con0 is now available

Press RETURN to get started.

User Access Verification

Username: babin  
Password:

Router>|

```
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#
Router(config)#
Router(config)#line console 0
Router(config-line)#password console
Router(config-line)#no login local
Router(config-line)#login
Router(config-line)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#exit
```

Router con0 is now available

Press RETURN to get started.

User Access Verification

Password:

Router>|

```
Router>enable
Router#
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#enable secret enable
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#exit
```


Router con0 is now available

Press RETURN to get started.

User Access Verification

Password:

```
Router>enable
Password:
Router#
Router#|
```



```
Router(config)#
Router(config)#
Router(config)#
Router(config)#
Router(config)#line vty 0 4
Router(config-line)#password telnet
Router(config-line)#login
Router(config-line)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#
```

```
C:\>
C:\>
C:\>telnet 50.0.0.1
Trying 50.0.0.1 ...Open

User Access Verification

Password:
Router>
Router>
Router>
```

```

ROUTER#sh ip int br
Interface                IP-Address      OK? Method Status        Protocol
Ethernet0/0              50.0.0.1       YES manual up            up
Ethernet0/1              unassigned     YES TFTP  down          down
Ethernet0/2              unassigned     YES TFTP  down          down
Ethernet0/3              unassigned     YES TFTP  down          down
ROUTER#
ROUTER#
ROUTER#config t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#username babin password babin
ROUTER(config)#
ROUTER(config)#line vty 0 4
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#
% Invalid input detected at '^' marker.
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#password telnet
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#

```

The screenshot shows a Windows Command Prompt window titled "Administrator: Command Prompt". The window displays the output of a ping command to the IP address 50.0.0.1. The output shows four successful replies with a time of 1ms and a TTL of 255. Ping statistics indicate that 4 packets were sent, 4 were received, and there was 0% loss. The approximate round trip times are: Minimum = 0ms, Maximum = 2ms, and Average = 1ms.

```

Administrator: Command Prompt
Microsoft Windows [Version 6.1.7601]
Copyright (c) 2009 Microsoft Corporation. All rights reserved.

C:\Users\user>ping 50.0.0.1

Pinging 50.0.0.1 with 32 bytes of data:
Reply from 50.0.0.1: bytes=32 time=2ms TTL=255
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Ping statistics for 50.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 2ms, Average = 1ms

C:\Users\user>

```

