Windows Server 2022

Server Installation & Troubleshooting in Hyper-V, OU & User Management, and GPO

MD ABUL BASHAR
Network and Server Administrator

TASK 1. Create the Virtual Machine (VM) in Hyper-V Manager

Open **Hyper-V Manager** Click **Start**, select and **Right click** select **New** >**Virtual Machine**. Click **Next**. **Specify Name and Location:** Enter a **Name ADDS DEMO** Click **Next**.

Specify Generation: Select **Generation 1** Click **Next**. **Assign Memory:** Enter the startup RAM 4096 Optionally, check **Use Dynamic Memory**. Click **Next**. **Configure Networking:** select **Not Connected** and configure it later. Click **Next**. **Connect Virtual Hard Disk:** Select **Create a virtual hard disk**. Specify the **Size 40 GB** Click **Next**. **Installation Options:** Select **Install an operating system from a bootable image file**. Click **Browse** and select **Windows Server 2022 ISO file**. Click **Next**.



Install Windows Server 2022 Datacenter (GUI):

First of all **Start the VM:** In Hyper-V Manager, right-click VM (**ADDS DEMO**) and select **Connect**. Then, in the VM Connection window, click **Start**. VM window to boot from the ISO. **Language/Region:** Click **Next**, then **Install now**. or click **I don't have a product key**. **Select Edition:** select **Windows Server 2022 Datacenter (Desktop Experience)** and Click **Next**. **Installation Type:** Select **Custom: Install Windows only (advanced)**. **Disk Selection:** Select the virtual hard disk from created (Drive T). Click **Next**. **Install** and Enter a complex password and click **Finish**.

TASK 2: Change Hostname:

Open **Server Manager**. Click **Local Server**. Click the computer name and then click **Change.**Enter **DC** > **Computer name** and click **OK**. Restart the server when prompted.



Set Static IP:

Open Control Panel > Network and Internet > Network and Sharing Center.

Right-click the network adapter **Ethernet** and select **Properties**. Select **Internet Protocol Version 4 (TCP/IPv4)** and click Properties. Select Use the following IP address and enter the details:

IP address: **192.168.1.10**

Subnet mask: **255.255.255.0** (Common for /24 networks)

Default gateway: **192.168.1.1**

Enter Preferred DNS server **192.168.1.10** Click OK.

TASK 3: Install AD DS Role using Server Manager and Promote this Server As a Domain Controller.



TASK4: Forward Lookup Zone (FLZ):

Open DNS Manager: Go to **Server Manager >Tools > DNS**.

Start New Zone Wizard: Expand DNS server, right-click **Forward Lookup Zones**, and select **New Zone.** Select **Primary Zone**. select "Store the zone in Active Directory click Next.Click **Finish** .



Reverse Lookup Zone (RLZ):

Start New Zone Wizard Right-click **Reverse Lookup Zones** and select **New Zone.**Select **Primary Zone**. Select **IPv4 Reverse Lookup Zone**. Enter the **network ID** 192.168.1 . Select **Allow only secure dynamic updates**. Click **Finish** .





Create Records (PTR): check the option **"Create associated pointer (PTR) record"**. rightclick and select **New Pointer (PTR).** to map an IP address to a hostname **(dc.bashar.com).**



TASK 5: Verify DNS by command: Press **win + R** open **cmd** in **AD DS Server.**



TASK 6: After Verification, Join another system to the domain.



TASK 7: Account Lockout Policy:

Setting: Account lockout threshold and set **Value: 3 invalid login attempts**